

C3 ADDON SDK DOCUMENTATION

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk>

Welcome to the Construct 3 JavaScript SDK documentation. The JavaScript SDK allows third-party developers to create new plugins, behaviors and effects for Construct 3. The Theme SDK also allows custom appearances for the Construct 3 editor. Please note not all SDK features are currently available. This documentation will be updated as new capabilities are rolled out.

Downloads

Last updated: *1st April 2022*

Plugin SDK files	c3-plugin-sdk-v1-10.zip Download now 49.53 KB
Behavior SDK files	c3-behavior-sdk-v1-6.zip Download now 5.83 KB
Effect SDK files	c3-effect-sdk-v1-1.zip Download now 1.09 KB
Editor theme SDK files	c3-theme-sdk-v1-0-1.zip Download now 3.01 KB

The zip files contain the files for an example custom plugin, behavior or theme. The files for an addon can be zipped and renamed [.c3addon](#) to directly test it in the Construct 3 editor, via the Addon Manager.

While developing addons, be sure to [use Developer Mode](#) with a local HTTP server. It makes it much quicker to test since you don't need to keep creating .c3addon files, and much easier to fix problems, which otherwise can prevent Construct 3 from starting up.

Custom importer API sample data

The plugin SDK download includes a sample plugin using the Custom Importer API. The following sample file can be drag-and-dropped in to Construct 3 to demonstrate reading a custom format.

customImporterSampleData.zip
[Download now 7.42 KB](#)

Supported SDK features

Only the documented features are supported in the SDK. Do not use undocumented features - they could change or be removed at any time. Additionally third-party developers should heed any warnings logged to the browser console about deprecated or unsupported features. In these case features are likely to be removed, and you should take action sooner rather than later.

Learning web technologies

The Addon SDK documentation assumes you have a basic knowledge of JavaScript. A basic knowledge of HTML and CSS may also be useful. This documentation does not attempt to teach you these technologies. If you're just starting out, we recommend the [MDN web docs](#) as a good place to start. It provides thorough documentation on all aspects of the web platform, and also includes guides for learning web development.

THE .C3ADDON FILE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/guide/c3addon-file>

Construct 3 addons are distributed as a .c3addon file. This is simply a .zip file renamed to end with .c3addon. You can rename a .c3addon file to .zip and inspect its contents, or create a .c3addon file by zipping some files and renaming it.

Structure of a .c3addon file

The files in a .c3addon for a plugin are arranged as follows. Note some features allow extra files to be added, but this is the minimal file structure for an empty plugin/behavior.

- c3runtime/ â€” subfolder for Construct 3 runtime files.
- lang/en-US.json â€” language file containing strings shown in the user interface. This is kept in a separate file to facilitate translation.
- aces.json â€” JSON data file that defines actions, conditions and expressions.
- addon.json â€” JSON data file with metadata about the addon.
- icon.svg â€” addon icon.
- plugin.js or behavior.js â€” class representing the plugin or behavior.
- type.js â€” class representing an object type of the plugin, or behavior type of the behavior, in the editor.
- instance.js â€” class representing an instance of the plugin, or behavior instance of the behavior, in the editor.

Specifying metadata

The basic metadata about your addon, such as its ID and type, is set in addon.json. See [Addon metadata](#) for more information.

Setting plugin information

For plugins, the detailed information about the plugin and its capabilities is set in plugin.js. See [Configuring plugins](#) for more information.

Setting behavior information

For behaviors, the detailed information about the behavior and its capabilities is set in behavior.js. See [Configuring behaviors](#) for more information.

Setting effect information

For effects, the detailed information about the effect and its capabilities is set using extra properties in `addon.json`. The effect itself is written in a `.fx` file. See [Configuring effects](#) for more information.

Defining actions, conditions and expressions

To define your plugin or behavior's actions, conditions and expressions (ACEs), they must be specified in `aces.json` and the corresponding language strings added in `en-US.json`. (Currently the language file must be in US English, but the fact it is in a separate file will help facilitate translation in future.)

For more information see [Defining actions, conditions and expressions](#).

ADDON METADATA

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/guide/addon-metadata>

The metadata for your addon, specifying details like its ID and type, is defined by `addon.json`. An example is shown below.

```
{
  "is-c3-addon": true,
  "type": "plugin",
  "name": "My custom plugin",
  "id": "MyCompany_MyAddon",
  "version": "1.0.0.0",
  "author": "Scirra",
  "website": "https://www.construct.net",
  "documentation": "https://www.construct.net",
  "description": "Example custom Construct 3 plugin.",
  "editor-scripts": [
    "plugin.js",
    "type.js",
    "instance.js"
  ],
  "file-list": [
    "c3runtime/plugin.js",
    "c3runtime/type.js",
    "c3runtime/instance.js",
    "c3runtime/conditions.js",
    "c3runtime/actions.js",
    "c3runtime/expressions.js",
    "lang/en-US.json",
    "aces.json",
    "addon.json",
    "icon.svg",
    "instance.js",
    "plugin.js",
    "type.js"
  ]
}
```

Note some of the information is duplicated elsewhere in the addon's files. This is because the editor reads this file before it loads any other files when asking the

user if they want to install the addon. Note information specified here, such as the ID, must exactly match everywhere else it is used.

Each field and its possible values are described below.

is-c3-addon

Boolean set to `true`. This is used by Construct 3 to identify valid addons.

type

One of `"plugin"`, `"behavior"`, `"effect"` or `"theme"`, indicating the kind of addon this is.

name

The displayed name of the addon, in English.

id

The unique ID of the addon. This is not displayed and is only used internally. This must not be used by any other addon ever published for Construct 3, and must never change after you first publish your addon. (The name is the only visible identifier of the addon in the Construct 3 editor, so that can be changed any time, but the ID must always be the same.) To ensure it is unique, it is recommended to use a vendor-specific prefix, e.g. `MyCompany_MyAddon`. It must match the ID set in `plugin.js`.

version

A string specifying the addon version in four parts (major, minor, patch, revision). Be sure to update this when releasing updates to your addon. It must match the version set in `plugin.js/behavior.js`.

author

A string identifying the author of the addon.

website

A string of a URL to the author's website. It is recommended to provide updates to the addon at this URL if any become available. The website should use HTTPS.

documentation

A string of a URL to the online documentation for the addon. It is important to provide documentation for your addon to be useful to users.

description

A string of a brief description of what the addon does, displayed when

prompting the user to install the addon.

editor-scripts

For plugins and behaviors only. An array of script files in the addon package to load in the editor. It is recommended to leave this at the default unless you have large editor dependency scripts, or if you want to minify your addon in to a single script. Note themes do not use editor scripts.

stylesheets

For themes only. An array of CSS files in the addon package to apply to the document. These are the CSS files that define the theme's appearance.

file-list

For developer mode addons only. A list of all files used by the addon. This is required for Developer Mode addons since there is no other mechanism for Construct to determine the list of files when serving files from a web server. Be sure to update this property if you add, rename or remove any files in your addon.

Additional properties for effects

When developing an effect addon, additional information about the effect is included in the addon.json file. For more information see [Configuring effects](#).

CONFIGURING PLUGINS

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/guide/configuring-plugins>

The main configuration for a plugin is set in `plugin.js`.

Plugin constants

The following constants are defined in the file-level scope:

```
const PLUGIN_ID = "MyCompany_MyAddon";
const PLUGIN_VERSION = "1.0.0.0";
const PLUGIN_CATEGORY = "general";
```

The ID and version constants must match the values specified in [addon.json](#).

PLUGIN_ID

This is a unique ID that identifies your plugin from all other addons. This must not be used by any other addon ever published for Construct 3. It must never change after you first publish your addon. (The name is the only visible identifier of the addon in the Construct 3 editor, so that can be changed any time, but the ID must always be the same.) To ensure it is unique, it is recommended to use a vendor-specific prefix, e.g. `MyCompany_MyAddon`.

PLUGIN_VERSION

A string specifying the addon version in four parts (major, minor, patch, revision). Be sure to update this when releasing updates to your addon, which must also be updated in `addon.json`.

PLUGIN_CATEGORY

The category for the plugin when displaying it in the *Create New Object Type* dialog. This must be one of `"data-and-storage"`, `"form-controls"`, `"general"`, `"input"`, `"media"`, `"monetisation"`, `"platform-specific"`, `"web"`, `"other"`.

Updating plugin identifiers

The main class declaration of the plugin looks like this:

```
const PLUGIN_CLASS = SDK.Plugins.MyCompany_MyAddon = class MyCustom
Plugin extends SDK.IPluginBase
```


Be sure to update the identifiers to describe your own plugin, in both the SDK namespace and the `class` name.

Updating in `type.js` and `instance.js`

Likewise in both `type.js` and `instance.js`, you must update the following:

- `PLUGIN_CLASS` to refer to your plugin's name
- The `class` name suffixed with `Type` or `Instance`. (For example the Audio plugin uses `AudioPlugin`, `AudioType` and `AudioInstance` as the three names.)

The plugin constructor

The main function of `plugin.js` is to define a class representing your plugin. In the class constructor, the configuration for the plugin is set via the `this._info` member, which is an [IPluginInfo](#) interface. The constructor also reads potentially translated strings from the language subsystem.

For more information about the possible plugin configurations, see the `IPluginInfo` reference.

Specifying plugin properties

The plugin properties appear in the Properties Bar when instances of the plugin are selected. To set which properties appear, pass an array of [PluginProperty](#) to `this._info.SetProperties`. An example is shown below. For more details see the `PluginProperty` reference.

```
this._info.SetProperties([
    new SDK.PluginProperty("integer", "test-property", 0)
]);
```

CONFIGURING BEHAVIORS

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/guide/configuring-behaviors>

The main configuration for a behavior is set in `behavior.js`.

Behavior constants

The following constants are defined in the file-level scope:

```
const BEHAVIOR_ID = "MyCompany_MyAddon";
const BEHAVIOR_VERSION = "1.0.0.0";
const BEHAVIOR_CATEGORY = "general";
```

The ID and version constants must match the values specified in [addon.json](#).

BEHAVIOR_ID

This is a unique ID that identifies your behavior from all other addons. This must not be used by any other addon ever published for Construct 3. It must never change after you first publish your addon. (The name is the only visible identifier of the addon in the Construct 3 editor, so that can be changed any time, but the ID must always be the same.) To ensure it is unique, it is recommended to use a vendor-specific prefix, e.g. `MyCompany_MyAddon`.

BEHAVIOR_VERSION

A string specifying the addon version in four parts (major, minor, patch, revision). Be sure to update this when releasing updates to your addon, which must also be updated in `addon.json`.

BEHAVIOR_CATEGORY

The category for the behavior when displaying it in the *Add behavior* dialog. This must be one of `"attributes"`, `"general"`, `"movements"`, `"other"`.

Updating behavior identifiers

The main class declaration of the behavior looks like this:

```
const BEHAVIOR_CLASS = SDK.Behaviors.MyCompany_MyAddon = class MyCu
```

Be sure to update the identifiers to describe your own behavior, in both the SDK namespace and the class name.

Updating in type.js and instance.js

Likewise in both type.js and instance.js, you must update the following:

- `BEHAVIOR_CLASS` to refer to your behavior's name
- The `class` name suffixed with `Type` or `Instance`. (For example the `Bullet` behavior uses `BulletBehavior`, `BulletType` and `BulletInstance` as the three names.)

The behavior constructor

The main function of behavior.js is to define a class representing your behavior. In the class constructor, the configuration for the behavior is set via the `this._info` member, which is an [IBehaviorInfo](#) interface. The constructor also reads potentially translated strings from the language subsystem.

For more information about the possible behavior configurations, see the [IBehaviorInfo](#) reference.

Specifying behavior properties

The behavior properties appear in the Properties Bar when instances using the behavior are selected. To set which properties appear, pass an array of [PluginProperty](#) to `this._info.SetProperties`. An example is shown below. For more details see the [PluginProperty](#) reference. (Note that behaviors use the same property class as plugins, hence re-using the `PluginProperty` class for behaviors.)

```
this._info.SetProperties([
  new SDK.PluginProperty("integer", "test-property", 0)
]);
```

CONFIGURING EFFECTS

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/guide/configuring-effects>

The main configuration for an effect is set by additional effect-specific properties in [addon.json](#). The additional properties used by effects are listed below.

category

The category the effect should appear in. This must be one of `"blend"`, `"color"`, `"distortion"`, `"normal-mapping"`, `"other"`.

blends-background

Boolean indicating whether the effect blends with the background. Objects and layers can use effects that blend with the background, but layouts cannot.

uses-depth

Boolean indicating whether the effect samples the depth buffer with the `samplerDepth` uniform. This is used for depth-based effects like fog.

cross-sampling

Boolean indicating whether a background-blending effect has inconsistent sampling of the background and foreground. A normal blending shader like Multiply will sample the background and foreground 1:1, so each foreground pixel samples only the background pixel it is rendered to. This is consistent sampling so `cross-sampling` should be `false`. However an effect that distorts the background, like Glass or a masking Warp effect, can sample different background pixels to the foreground pixel being rendered, so should set `cross-sampling` to `true`. This must be specified so the effect compositor can ensure the correct result is rendered when this happens.

preserves-opaqueness

Boolean indicating whether the effect preserves opaque pixels, i.e. every input pixel with an alpha of 1 is also output with an alpha of 1. This is true for most color-altering effects, but not for most distorting effects, since in some cases a previously opaque pixel will be distorted in to a transparent area of the texture. This information is not currently used, but is important for front-to-back rendering algorithms.

animated

Boolean indicating whether the effect is animated, i.e. changes over time using

the `seconds` uniform. This is used to ensure Construct keeps redrawing the screen if an animated effect is visible.

must-predraw

Boolean indicating whether to force the pre-draw step. Sometimes Construct tries to optimise effect rendering by directly rendering an object with the shader applied. Setting this flag forces Construct to first render the object to an intermediate surface, which is necessary for some kinds of effect.

extend-box

Amount to extend the rendered box horizontally and vertically. Normally the effect is clipped to the object's bounding box, but some effects like Warp need to be able to render a short distance outside of that for the correct result. This property lets you extend the rendered box by a number of pixels. This property uses `"horizontal"` and `"vertical"` sub-properties, e.g. `"extend-box": { "horizontal": 30, "vertical": 30 }`

is-deprecated

Boolean to indicate a deprecated effect. This hides the effect from the *Add effect* dialog, but allows existing projects to continue using it. This allows an effect to be phased out without breaking projects.

parameters

An array of parameters that the effect uses. See the next section for more information.

Effect parameters

The `parameters` array in `addon.json` specifies a list of parameters that are passed to the shader as uniforms. These can be used to customise the appearance of the effect, and can also be changed at runtime. Each parameter is specified as an object with the following properties.

id

A string identifying this parameter.

c2id

The corresponding ID used by Construct 2 if this is not the same as the `id`. Note for color parameters, this can be a comma-separated list of the three parameter IDs previously used for the red, green and blue components, e.g. `"red,green,blue"`.

type

The type of the effect parameter. This can be one of `"float"`, `"percent"` or `"color"`. Floats pass a simple number. Percent displays a percentage in the 0-100 range but passes a float in the 0-1 range to the shader. Color shows a color picker and passes a `vec3` with components in the 0-1 range to the shader.

initial-value

The initial value of the shader uniform, in the format the shader uses it (i.e. 0-1 range for percent parameters). For color parameters, use a 3-element array, e.g. `[1, 0, 0]` for red.

uniform

The name of the corresponding uniform in the shader. The uniform must be declared in GLSL with this name. It can use whichever precision you want, but the uniform type must be `vec3` for color parameters, otherwise `float`.

interpolatable

Set to `true` so the property can be supported by timelines.

Shader uniforms

The shader is written in a GLSL (OpenGL Shading Language) fragment shader and interpreted by the browser's WebGL implementation. Note although Construct supports WebGL 2 where available, shaders should be written for WebGL 1 GLSL for compatibility with all systems. As with normal fragment shaders, the output is written to the special `gl_FragColor` variable.

The current foreground texture co-ordinate is provided in the special `varying` variable `vTex`. This is normally used to read the foreground texture, but it is actually optional (in case you want to write a shader that generates all of its output without reference to the foreground texture at all). All other uniforms are optional, and are documented below. The full uniform declaration is included with the recommended precision.

uniform lowp sampler2D samplerFront;

The foreground texture sampler, to be sampled at `vTex`.

uniform mediump vec2 srcStart;

uniform mediump vec2 srcEnd;

The current foreground rectangle being rendered, in texture co-ordinates. Note this is clamped as the object reaches the edge of the viewport. These are mainly useful for calculating the background sampling position.

uniform mediump vec2 srcOriginStart;
uniform mediump vec2 srcOriginEnd;

The current foreground source rectangle being rendered, in texture co-ordinates. This is not clamped, so can cover a rectangle that leaves the viewport. These are mainly useful for calculating the current sampling position relative to the object being rendered, without changing as the object clips against the viewport.

uniform mediump vec2 layoutStart;
uniform mediump vec2 layoutEnd;

The current foreground source rectangle being rendered, in layout co-ordinates. This allows the current fragment's position in the layout to be calculated.

uniform lowp sampler2D samplerBack;

The background texture sampler used for background-blending effects. The `blends-background` property in `addon.json` should also be set to `true` before using this. For the correct way to sample the background, see the next section.

uniform lowp sampler2D samplerDepth;

The depth texture sampler used for depth-based effects. The `uses-depth` property in `addon.json` should also be set to `true` before using this. The depth texture is the same size as the background texture, so this is sampled similarly to `samplerBack`. See the next section for more details.

uniform mediump vec2 destStart;
uniform mediump vec2 destEnd;

The current background rectangle being rendered to, in texture co-ordinates, for background-blending effects. For the correct way to sample the background, see the next section.

uniform highp float seconds;

The time in seconds since the runtime started. This can be used for animated effects. The `animated` property in `addon.json` should be set to `true`.

Note `highp` can only be used on certain platforms. To work across all systems, check `#ifdef GL_FRAGMENT_PRECISION_HIGH` to see if `highp` is supported, else fall back to using `mediump`.

uniform mediump vec2 pixelSize;

The size of a texel in the foreground texture in texture co-ordinates. This allows

calculating distances in pixels rather than texture co-ordinates.

uniform mediump float layerScale;

The current layer scale as a factor (i.e. 1 is unscaled). This is useful to ensure effects scale according to zoom.

uniform mediump float layerAngle;

The current layer angle in radians.

uniform mediump float devicePixelRatio;

The value of [devicePixelRatio](#) in the browser, which is the number of device pixels per CSS pixel. This may be necessary in some effects to handle high-DPI displays.

Useful shader calculations

Some common calculations done with the available uniforms are listed below.

To sample the foreground pixel:

```
lowp vec4 front = texture2D(samplerFront, vTex);
```

To sample an adjacent pixel, offset by the pixel size:

```
// sample next pixel to the right
lowp vec4 next = texture2D(samplerFront, vTex + vec2(pixelSize.x,
0.0));
```

To calculate the position to sample the background, find the normalised position `n` of `vTex` in the foreground rectangle, and apply that to the background rectangle:

```
mediump vec2 n = (vTex - srcStart) / (srcEnd - srcStart);
lowp vec4 back = texture2D(samplerBack, mix(destStart, destEnd, n)
);
```

Sampling the depth buffer works similarly to sampling the background, but only provides one component, so just read the `r` value. Note that the value in the depth buffer is normalized (0-1 range) and does not linearly correspond to distance. To get a linearized Z value for a depth sample, use the calculation below.

This calculation depends on the near and far Z distances, which are

currently hard-coded to 1 and 10000 in Construct's engine.

```
mediump float zNear = 1.0;
mediump float zFar = 10000.0;

mediump vec2 n = (vTex - srcStart) / (srcEnd - srcStart);
mediump float depthSample = texture2D(samplerDepth, mix(destStart,
destEnd, n)).r;
mediump float zLinear = zNear * zFar / (zFar + depthSample * (zNear - zFar));
```

To calculate the current texture co-ordinate relative to the object being rendered, without being affected by clipping at the edge of the viewport, use the original source rectangle:

```
mediump vec2 srcOriginSize = srcOriginEnd - srcOriginStart;
mediump vec2 n = ((vTex - srcOriginStart) / srcOriginSize);
```

To calculate the current layout co-ordinates being rendered, add an extra step to interpolate `n` across the layout rectangle:

```
mediump vec2 srcOriginSize = srcOriginEnd - srcOriginStart;
mediump vec2 n = ((vTex - srcOriginStart) / srcOriginSize);
mediump vec2 l = mix(layoutStart, layoutEnd, n);
```

Construct renders using premultiplied alpha. Often it is convenient to modify the RGB components without premultiplication. To do this, divide by alpha to unpremultiply the color, but be sure not to divide by zero.

```
lowp vec4 front = texture2D(samplerFront, vTex);
lowp float a = front.a;

// unpremultiply
if (a != 0.0)
    front.rgb /= a;

// ...modify unpremultiplied front color...

// premultiply again
front.rgb *= a;
```

DEFINING ACTIONS, CONDITIONS AND EXPRESSIONS

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/guide/defining-aces>

The set of actions, conditions and expressions which are available in your addon is defined in aces.json. The term "ACE" is used to refer to an action, condition or expression in general. ACEs are grouped by category. The overall structure of the file format is as follows.

```
{
  "category1": {
    "conditions": [
      condition1,
      condition2,
      ...
    ],
    "actions": [
      action1,
      action2,
      ...
    ],
    "expressions": [
      expression1,
      expression2,
      ...
    ]
  },
  "category2": {
    "conditions": [
      ...
    ],
    "actions": [
      ...
    ],
    "expressions": [
      ...
    ]
  }
}
```

```
}
```

Note that Construct 2 uses numbers for IDs, whereas Construct 3 uses strings. These strings are then also used to identify related language strings in the language file.

Never delete ACES after release

Once you have released your addon, never delete any actions, conditions or expressions from it. This will corrupt everyone's projects that use your addon, because Construct will no longer be able to find the deleted action, condition or expression in your addon. Instead mark the features deprecated so they are hidden.

Categories

Each category key is the category ID. This is not displayed in the editor; the string to display is looked up in the language file.

For behaviors only, a default category of an empty string may be used. This category will use the behavior name. Other categories may still be used, in which case Construct 3 will append the category name after the behavior name, e.g. "MyBehaviorName: My category".

Common properties of ACE definitions

Each entry in the `"conditions"`, `"actions"` and `"expressions"` arrays is a JSON object which defines a single condition, action or expression. An example minimal condition definition for the System *Every Tick* condition is shown below.

```
{
  "id": "every-tick",
  "scriptName": "EveryTick"
}
```

The `id` and `scriptName` are the only required properties for conditions and actions. Expressions require `id`, `expressionName` and `returnType`. All other properties are optional.

The definitions for conditions, actions and expressions all share a few common properties. These are detailed below. Then the properties specific to each kind is documented after that.

id

A string specifying a unique ID for the ACE. This is used in the language file. By convention this is lowercase with dashes for separators, e.g. "my-condition".

c2id

If you are porting a Construct 2 addon to Construct 3, put the corresponding numerical ID that the Construct 2 addon used here. This allows Construct 3 to import Construct 2 projects using your addon.

scriptName / expressionName

The name of the function in the runtime script for this ACE. Note for expressions, use `expressionName` instead, which also defines the name typed by the user in expressions.

isDeprecated

Set to true to deprecate the ACE. This hides it in the editor, but allows existing projects to continue using it.

highlight

Set to true to highlight the ACE in the condition/action/expression picker dialogs. This should only be used for the most regularly used ACEs, to help users pick them out from the list easily.

params

An array of parameter definitions. See the section below on parameters. This can be omitted if the ACE does not use any parameters.

Condition definitions

Condition definitions can also use the following properties.

isTrigger

Specifies a trigger condition. This appears with an arrow in the event sheet. Instead of being evaluated every tick, triggers only run when they are explicitly triggered by a runtime call.

isFakeTrigger

Specifies a fake trigger. This appears identical to a trigger in the event sheet, but is actually evaluated every tick. This is useful for conditions which are true for a single tick, such as for APIs which must poll a value every tick.

isStatic

Normally, the condition runtime method is executed once per picked instance. If the condition is marked static, the runtime method is executed once only, on the object type class. This means the runtime method must also implement the instance picking entirely itself, including respecting negation and OR blocks.

isLooping

Display an icon in the event sheet to indicate the condition loops. This should only be used with conditions which implement re-triggering.

isInvertible

Allow the condition to be inverted in the event sheet. Set to `false` to disable invert.

isCompatibleWithTriggers

Allow the condition to be used in the same branch as a trigger. Set to `false` if the condition does not make sense when used in a trigger, such as the *Trigger once* condition.

Action definitions

Action definitions can also use the following properties.

isAsync

Set to `true` to mark the action as asynchronous. Make the action method an `async` function, and the system *Wait for previous actions to complete* action will be able to wait for the action as well.

Expression definitions

Expressions work slightly differently to conditions and actions: they must specify a `returnType`, and instead of using a `scriptName` they specify an `expressionName` which doubles as both what is typed for the expression as well as the runtime script function name.

returnType

One of `"number"`, `"string"`, `"any"`. The runtime function must return the corresponding type, and `"any"` must still return either a number or a string.

isVariadicParameters

If `true`, Construct 3 will allow the user to enter any number of parameters beyond those defined. In other words the parameters (if any) listed in

"params" are required, but this flag enables adding further "any" type parameters beyond the end.

Parameter definitions

ACEs can all define which parameters they use with the "params" property. This property should be set to an array of parameter definition objects. Below shows an example for the System *Compare two values* condition.

```
{
  "id": "compare-two-values",
  "scriptName": "Compare",
  "params": [
    { "id": "first-value", "type": "any" },
    { "id": "comparison", "type": "cmp" },
    { "id": "second-value", "type": "any" }
  ]
}
```

Note that expressions can only use "number", "string" or "any" parameter types.

id

A string with a unique identifier for this parameter. This is used to refer to the parameter in the language file.

c2id

In some circumstances, it is necessary to specify which Construct 2 parameter ID a parameter corresponds to. However normally it can be inferred by the parameter index.

type

The parameter type. Expressions can only use "number", "string" or "any". However conditions and actions have the following options available:

- "number" â€” a number parameter
- "string" â€” a string parameter
- "any" â€” either a number or a string

- `"boolean"` â€” a boolean parameter, displayed as a checkbox
- `"combo"` â€” a dropdown list. Items must be specified with the `"items"` property.
- `"cmp"` â€” a dropdown list with comparison options like "equal to", "less than" etc.
- `"object"` â€” an object picker. The types of plugin to show can be filtered using an optional `"allowedPluginIds"` property.
- `"objectname"` â€” a string parameter which is interpreted as an object name
- `"layer"` â€” a string parameter which is interpreted as a layer name
- `"layout"` â€” a dropdown list with every layout in the project
- `"keyb"` â€” a keyboard key picker
- `"instancevar"` â€” a dropdown list with the non-boolean instance variables the object has
- `"instancevarbool"` â€” a dropdown list with the boolean instance variables the object has
- `"eventvar"` â€” a dropdown list with non-boolean event variables in scope
- `"eventvarbool"` â€” a dropdown list with boolean event variables in scope
- `"animation"` â€” a string parameter which is interpreted as an animation name in the object
- `"objinstancevar"` â€” a dropdown list with non-boolean instance variables available in a prior `"object"` parameter. Only valid when preceded by an `"object"` parameter.

initialValue

A string which is used as the initial expression for expression-based parameters. Note this is still a string for `"number"` type parameters. It can contain any valid expression for the parameter, such as `"1 + 1"`. For `"boolean"` parameters, use a string of either `"true"` or `"false"`. For `"combo"` parameters, this is the initial item ID.

items

Only valid with the `"combo"` type. Set to an array of item IDs available in the dropdown list. The actual displayed text for the items is defined in the language file.

allowedPluginIds

Optional and only valid with the `"object"` type. Set to an array of plugin IDs allowed to be shown by the object picker. For example, use `["Sprite"]` to only allow the object parameter to select a Sprite.

Language strings

The `aces.json` file does not include any strings displayed in the editor UI. These are all kept in a separate language file to facilitate translation. Therefore to finish adding ACEs, the relevant UI strings like the list name and description must be added to the language file. See [The language file](#) for more information.

THE LANGUAGE FILE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/guide/language-file>

In the .c3addon file, en-US.json is the default language file containing all the addon's strings that are shown in the editor UI in a JSON format. Moving these strings to a separate file makes it possible for the software to be fully translated.

All strings must be provided in US English (hence the filename en-US.json) since this is the default language of Construct 3, and the common language from which all other languages are translated.

Overall structure

The overall structure of the language file is as follows, taken from the plugin SDK template. Note that in general, the language file uses an ID as a key on the left, and the string to display as the value on the right.

```
{
  "languageTag": "en-US",
  "fileDescription": "Strings for MyCustomPlugin.",
  "text": {
    "plugins": {
      "mycompany_myaddon": {
        "name": "My Custom Plugin",
        "description": "Description for my custom plugin.",
        "help-url": "https://www.scirra.com",
        "properties": {
          "test-property": {
            "name": "Test property",
            "desc": "A test number property. Displayed by 'Alert' action."
          }
        }
      },
      "aceCategories": {
        "custom": "Custom"
      },
      "conditions": {
        "is-large-number": {
          "list-name": "Is large number",
          "display-text": "[i]{0}[/i] is a large number",
          "description": "Test if a number is greater than 100."
        }
      }
    }
  }
}
```

```
"params": {
  "number": {
    "name": "Number",
    "desc": "Number to test if greater than 100."
  }
},
"actions": {
  "do-alert": {
    "list-name": "Do alert",
    "display-text": "Do alert",
    "description": "Do a dummy alert."
  }
},
"expressions": {
  "double": {
    "description": "Double a number.",
    "translated-name": "Double",
    "params": {
      "number": {
        "name": "Number",
        "desc": "The number to double."
      }
    }
  }
}
}
```

Required fields

"languageTag" must be "en-US".

"fileDescription" is not used in the editor. It provides a hint to translators. It can simply say "Strings for [addon name]".

"text" represents the root node of the string tree, and "plugins" represents strings for all plugins. These should be left as they are.

"mycompany_myaddon" should be the lowercase addon ID. Note if your addon ID contains any uppercase characters, they should be lowercased for this

key in the language file. The remaining strings all belong inside this key, since it represents your plugin.

`"name"` is the name of your plugin as it appears in the editor. This can be changed at any time, but the plugin ID should not be changed after release.

`"description"` is a short sentence or two describing what your plugin does.

`"help-url"` is a URL to documentation or support for your plugin.

Note: themes only need to use the `"name"`, `"description"` and `"help-url"` fields.

Strings for properties/parameters

For each [PluginProperty](#) your plugin uses, there must be a key with the property ID under `"properties"`. For effects, there must be a key with the parameter ID under a `"parameters"` instead, but it otherwise works the same. The required strings for each property are:

- `"name"` – the name of the property, which appears to the left of the field
- `"desc"` – the property description, which appears in the footer of the Properties Bar

For example given the following property:

```
new SDK.PluginProperty("integer", "test-property", 0)
```

The following language strings can be used under the `"properties"` key:

```
"test-property": {
  "name": "Test property",
  "desc": "A test number property. Displayed by 'Alert' action."
}
```

Some properties require additional keys.

Combo properties

The `"combo"` property type needs an extra `"items"` key to set the visible name of each item. Each key underneath this should be the ID of the combo item, and its value the name to use. Here is an example from the Audio plugin. The property is created as:

```
new SDK.PluginProperty("combo", "timescale-audio", {
```

```
    initialValue: "off",
    items: ["off", "sounds-only", "sounds-and-music"]
  })
```

Note the items defined here are IDs rather than displayed strings. The strings to display are set in the language file like this:

```
"timescale-audio": {
  "name": "Timescale audio",
  "desc": "Choose whether the audio playback rate changes with the t
ime scale.",
  "items": {
    "off": "Off",
    "sounds-only": "On (sounds only)",
    "sounds-and-music": "On (sounds and music)"
  }
}
```

Link properties

The `"link"` property type needs an extra `"link-text"` key to set the text of the clickable link. An example is below.

```
"make-original-size": {
  "name": "Size",
  "desc": "Click to set the object to the same size as its image.",
  "link-text": "Make 1:1"
}
```

Category names

When [defining ACEs](#), category IDs are used rather than category names. The `"aceCategories"` key defines the displayed name of each category. The following example displays all ACEs in the category ID `"customCategory"` as being in a section labelled `"My custom category"`.

```
"aceCategories": {
  "customCategory": "My custom category"
}
```

Category names are shared across actions, conditions and expressions.

ACE strings

Strings for conditions, actions and expressions are listed in the keys `"conditions"`, `"actions"` and `"expressions"` respectively. Note they are not sorted by category here; each section lists all ACEs of that type.

Similar to properties, each key under each section is the ID of the action, condition or expression. As with the definitions themselves, actions and conditions work slightly differently to expressions.

Action and condition strings

The required keys are:

- `"list-name"` â€” the name that appears in the condition/action picker dialog.
- `"display-text"` â€” the text that appears in the event sheet. You can use simple BBCode tags like `[b]` and `[i]`, and use `{0}`, `{1}` etc. as parameter placeholders. (There must be one parameter placeholder per parameter.) For behaviors only, the placeholder `{my}` is substituted for the behavior name and icon.
- `"description"` â€” a description of the action or condition, which appears as a tip at the top of the condition/action picker dialog.

Expression strings

The required keys are:

- `"description"` â€” the description that appears in the expressions dictionary, which lists all available expressions.
- `"translated-name"` â€” the translated name of the expression name. In the en-US file, this should simply match the expression name from the expression definition. This key mainly exists so it can be changed in other languages, making it possible to translate expressions in some contexts. Note when actually typing an expression the non-translated expression name must always be used.

Parameters

Actions, conditions and expressions can omit the `"params"` key if they have no parameters. However if they have any parameters this key must be present, and each parameter must have its own key inside with the ID of the parameter. Similar to the plugin properties, each key must have a `"name"`, `"desc"` and for combo parameters, `"items"` (which work the same as `"combo"` property types: each item ID maps to its display text).

Example

The *Is large number* condition in the plugin SDK uses the following definition in `aces.json`:

```
{
  "id": "is-large-number",
  "scriptName": "IsLargeNumber",
  "highlight": true,
  "params": [
    {
      "id": "number",
      "type": "number"
    }
  ]
}
```

Its corresponding language strings are defined in `en-US.json` as follows:

```
"is-large-number": {
  "list-name": "Is large number",
  "display-text": "[i]{0}[/i] is a large number",
  "description": "Test if a number is greater than 100.",
  "params": {
    "number": {
      "name": "Number",
      "desc": "Number to test if greater than 100."
    }
  }
}
```

RUNTIME SCRIPTS

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/guide/runtime-scripts>

Plugin and behavior addons have separate scripts that run in the context of the runtime (the Construct game engine) rather than the editor.

Effects don't use runtime scripts. They will work in both runtimes without needing any changes.

Runtime documentation

For a reference on the C3 runtime, please refer to the section on the [Runtime API reference](#).

C3 runtime API calls

In the runtime, much code is shared with the editor, such as the WebGL renderer class. However in the editor, API calls are behind a special SDK layer (usually within the `SDK` namespace), for security and compatibility reasons. On the other hand the runtime does not use a special SDK layer, for maximum performance and flexibility; these calls are usually within the `C3` namespace. Be sure to use the right namespace depending on the context.

The runtime APIs allow access to all parts of the engine. Do not use undocumented features, or other object's properties or methods beginning with an underscore, which is a convention used to indicate private features. These features are subject to change at any time, including backwards-incompatible changes, or complete removal, that may break your addon. If your addon uses these features and is broken by a change, we will not offer any support, since you should not have been using them in the first place. If users complain about the breakage, we will forward them on to you. It is important to allow flexibility in the core engine to ensure we can make optimisations, do necessary refactoring, implement new features, and so on, which is why we will only support the documented, public APIs.

DOM calls in the C3 runtime

A major architectural feature of the runtime is the ability to host the runtime in a dedicated worker, off the main thread. In this mode it renders using

OffscreenCanvas. With the modern web platform, many functions and classes are available in dedicated workers, and more are being added over time. Refer to [this MDN guide](#) on available APIs in workers.

Providing your addon's runtime calls only use APIs available in a worker, such as `fetch()` or IndexedDB, then it will not need any changes to support a worker. However if it does use APIs not normally available in a worker, then it will need some changes.

The principle behind making calls to the main thread in the C3 runtime is to split the runtime scripts in to two halves: the runtime side (that runs in the worker), and the DOM side (that runs on the main thread where the document is). The DOM side has full access to all browser APIs. The runtime side can issue DOM calls using a specially-designed messaging API built in to the runtime. Essentially instead of making a call, you simply post a message with parameters for the call to the script on the DOM side, where the API call is really made. The DOM side can then send a message back with a result, or send messages to the runtime on its own, such as in response to events. The messaging APIs make this relatively straightforward. However one consequence to note is that a synchronous API call will become asynchronous, since the process of messaging to or from a worker is asynchronous.

Once this approach is used, there is no need to change anything to support the normal (non-Worker) mode. In this case both scripts will run in the same context and the messaging API will simply forward messages within the same context too. Therefore this one approach covers both cases, and ensures code works identically regardless of whether the runtime is hosted in the main thread or a worker.

Using a DOM script

By default Construct 3 assumes no DOM scripts are used. If you want to use one, use the following call on `IPluginInfo` to enable one:

```
this._info.SetDOMSideScripts(["c3runtime/domSide.js"]);
```

Since an array of script paths is used, if you have a lot of DOM code, you can split it across different files. Don't forget to add these files to the file list in

```
addon.json.
```

For documentation on the DOM messaging APIs, refer to [DOMElementHandler](#) (used in `domSide.js`), [SDKDOMPluginBase](#) (used in `plugin.js`), and [SDKDOMInstanceBase](#) (used in `instance.js`).

For an example demonstrating how to get started, see the `domElementPlugin`

template in the C3 plugin SDK download. This demonstrates using the above APIs to create a simple `<button>` element in the DOM with a custom button text, and firing an *On clicked* trigger, with support for running in a Web Worker.

Supporting the debugger

Plugins and behaviors can display custom properties in the debugger by overriding the `GetDebuggerProperties()` method of the instance class. It should return an array of property sections of the form `{ title, properties }`, where `title` is a string of the section title and `properties` is an array of property objects. Each property object is of the form `{ name, value }` with an optional `onedit` callback. The name must be a string, and the value can be a string, number or boolean.

Editing properties

If an `onedit` callback is omitted, the debugger displays the property as read-only. If it is provided, the debugger allows the property to be edited. If it is changed, the callback is run with the new value as a parameter.

In many cases, editing a property does the equivalent of an action. To conveniently manage your code, you can implement actions as methods on your instance class, and call the same method from both the action and the debugger edit handler. These methods can then also be re-used for other interfaces, such as the scripting interface, or an API for other addons to call.

Translation

By default, property section titles and property names are interpreted as language string keys. This allows them to be translated by looking them up in your addon's language file. Note property values do not have any special treatment. You can bypass the language file lookup by prefixing the string with a dollar character `$`, e.g. the property name `"plugins.sprite.debugger.foo"` will look up a string in the language file, but `"$foo"` will simply display the string `foo`.

The debugger runs in a separate context to the editor, and as such not all language strings are available. The language keys available in the debugger are:

- The addon name
- All property names
- All combo property items
- Everything under the "debugger" key

In general, if you need a language string for the debugger, simply place it under

the "debugger" key, e.g. at "plugins.sprite.debugger.foo".

Sample code

The following code is used by the Sprite plugin to display its animation-related debugger properties. Notice how it uses language keys and calls actions to update properties.

```
GetDebuggerProperties()
{
  const Acts = C3.Plugins.Sprite.Acts;
  const prefix = "plugins.sprite.debugger.animation-properties";
  return [{
    title: prefix + ".title",
    properties: [
      {name: prefix + ".current-animation", value: this._currentAnimation.GetName(), onedit: v => this._SetAnimation(v)},
      {name: prefix + ".current-frame", value: this._currentFrameIndex, onedit: v => this._SetAnimationFrame(v)},
      {name: prefix + ".is-playing", value: this._isAnimationPlaying, onedit: v => this._SetAnimationPlaying(v)},
      {name: prefix + ".speed", value: this._currentAnimationSpeed, onedit: v => this._SetAnimationSpeed(v)},
      {name: prefix + ".repeats", value: this._animationRepeats, onedit: v => this._SetAnimationRepeats(v)}
    ]
  }];
}
```

SCRIPT MINIFICATION

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/guide/script-minification>

Projects exported with "Minify script" enabled will run all script through an advanced minifier. This includes mangling property names to achieve maximum compression, and increase the difficulty of reverse engineering. The process uses Google Closure Compiler's advanced optimisations mode.

JavaScript in addons needs to be specially written to take in to account the minifier if they use external APIs that are not processed by the same minifier. Once you are familiar with what the minifier does, this is a straightforward process. Be sure to test your addon with minification to ensure it won't be broken when users export with minification enabled.

This process also affects JavaScript code that users write in Construct the same way as it affects your addon. Therefore for details on how to handle script minification, refer to the [guide on exporting with advanced minification](#) from the scripting section of the Construct manual.

PORTING CONSTRUCT 2 PLUGINS/BEHAVIORS

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/guide/porting-c2-addons>

To port a Construct 2 plugin or behavior to Construct 3, use the following checklist.

- 1 Start by copying the template SDK to a new folder.
- 2 You can directly copy the runtime.js from your Construct 2 addon to c2runtime/runtime.js. Usually the runtime script does not require any modifications.
- 3 Update the [addon metadata](#) in addon.json.
- 4 Update the icon. An SVG icon is preferable. The .ico files Construct 2 uses are not supported in Construct 3, but you can use a PNG icon. Just delete icon.svg, add icon.png, and call `this._info.SetIcon("icon.png", "image/png");` in the plugin/behavior constructor.
- 5 Update the plugin/behavior constants and identifiers in plugin.js/behavior.js, type.js and instance.js, as described in [configuring plugins/configuring behaviors](#).
- 6 Match your Construct 2 addon's configuration by making calls to [IPluginInfo/IBehaviorInfo](#) in the addon constructor. For example if your Construct 2 plugin was a single-global plugin, the Construct 3 plugin should call `this._info.SetIsSingleGlobal(true);` in the plugin constructor.
- 7 Add equivalent properties as the Construct 2 addon has. See *Specifying plugin properties* in [configuring plugins](#). (The process is identical for behaviors.)
- 8 Create corresponding action, condition and expression definitions. See [defining actions, conditions and expressions](#). The key point to ensure Construct 2 projects using your addon can be imported to Construct 3 is:
 - 9 Give every action, condition and expression a new `id` based on a string.
 - 10 Also set the `c2id` property to the corresponding numeric ID that the Construct 2 addon used
- 11 Update [the language file](#) to contain the UI strings for the addon, properties, and ACEs.
- 12 Consider porting the runtime script to the C3 runtime.

Once complete, zip all the addon files and rename the .zip to .c3addon. You should now have a addon you can install via the Addon Manager in Construct 3.

THEME ADDONS

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/guide/themes>

Construct 3 allows theme addons, which simply add some custom stylesheets to the document. This allows a great deal of flexibility in customising the appearance of the Construct 3 editor. Any features of CSS can be used to alter the UI appearance. You can use browser developer tools to identify the classes and DOM structure used in the editor, and override the styles Construct 3 applies by default in your own stylesheet.

Themes are based on the same [.c3addon file](#) that plugins and behaviors use, although with fewer necessary files. As you can see in the theme SDK download, all you need are `lang/en-US.json`, `addon.json`, an icon, and a stylesheet. Note your [addon metadata](#) must also contain a list of `stylesheets` â€” this is just a list of the CSS files to add to the document when your theme is applied.

As with other kinds of addon, you can [test themes as developer addons](#) for quicker development.

Tips for developing themes

- Construct 3 uses a range of CSS variables (aka custom properties) to more easily customise certain parts of the UI. These also allow customisation of colors not in the DOM, such as the Layout View (which is rendered with WebGL). The available CSS variables are listed in comments in the theme SDK. Note colors in CSS variables must always be written in hex format (`#000000`), except for layout view colors which can use `rgba()` syntax. (Other CSS properties can use any syntax; only CSS variables are restricted, since they are sometimes read from JavaScript.)
- Avoid making significant alterations to layout. In many cases Construct 3's code assumes certain layout of elements. Additionally it is time consuming to test layout changes work across every part of the UI. For example Construct 3 has over 50 dialogs, and testing all the dialogs still appear correctly after a change is a lot of work. On the other hand, cosmetic changes like colors and borders are usually safe.
- Be sure to also test your theme on mobile. Construct 3 uses different paradigms and layouts in a number of places when adapting to smaller mobile displays, and you should check your theme still appears correctly in that mode.
- Be wary of styles that could have a performance impact. For example heavy use of shadows, effects (such as blurs or other filters) or animations, could be taxing on the CPU or GPU. Fewer people will use your theme if it slows down

their device, so try to make sure your styles are used efficiently.

Using themes

Once you have installed a theme add-on, you can start using it by selecting it from the Settings dialog. Note this involves restarting Construct 3 twice: once when the add-on is installed, after which it appears in the Settings dialog, and then again after selecting it in the Settings dialog.

ENABLING DEVELOPER MODE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/guide/enabling-developer-mode>

Construct 3's Developer Mode enables extra testing features for developers, such as a special [addon testing mode](#).

To enable Developer Mode, open Construct 3's settings dialog and click or tap the dialog caption 10 times. A prompt will appear asking if you want to show developer mode settings. Click OK.

Now in the settings dialog there should be a checkbox named *Enable developer mode*. Tick the checkbox, close the settings dialog and restart Construct 3. You are now using Developer Mode.

TESTING ADDONS IN DEVELOPER MODE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/guide/using-developer-mode>

While developing an addon, it is inconvenient to have to package and install a new .c3addon file every time you make a change. To make testing easier, you can load an addon from a local web server. This means every time you reload Construct 3, it re-loads the latest version of your addon from your local web server, saving you from having to make any .c3addon packages.

Step 1: enable Developer Mode

For these steps to work, you must first [enable Developer Mode](#).

Step 2: start a local web server

There are many ways to run a local web server, e.g. with a Chrome extension, or a standalone server like nginx. Refer to your chosen server's documentation for installation and configuration.

Your local web server must host on *localhost*. Construct 3 will refuse to load addons from any other origin. You can host on any port, but it is recommended to use a port in the ephemeral port range 49152-65535.

The local web server must serve all the addon files with [CORS](#) (Cross-Origin Resource Sharing) enabled for Construct 3 to be able to load them, since it will be making a cross-domain request. In practice this means adding this HTTP header to the server response:

```
Access-Control-Allow-Origin: *
```

To do this you need to enable CORS if your web server provides a setting for that, or manually specify the header. For example in nginx, add the following directive in your server location section:

```
add_header Access-Control-Allow-Origin *;
```

You may also wish to review the caching headers to ensure your local server does not return old cached files. Disabling caching entirely will ensure Construct 3 always receives the latest files.

Once the server is fully configured, simply host the contents of the [c3addon file](#) in

a folder on your local web server. For example the URL `http://localhost:65432/myaddon/addon.json` should serve the `addon.json` file for your addon.

In modern browsers, `http://localhost` counts as a secure context even though it does not use HTTPS. Therefore you should not need to set up SSL/TLS for the local server.

Step 3: update `addon.json` to include file list

Normally when files are extracted from the zip-format `.c3addon` file, Construct 3 can obtain a file list from the zip. However when loading from a local web server, Construct 3 needs another way to identify all available files. So you must update `addon.json` to include a complete file list. For more information see the section *Developer mode addons* in [Addon metadata](#).

The file list can be left in when distributing your `.c3addon` file – there's no need to later remove it.

Step 4: install the developer mode addon

In Construct 3, open the Addon Manager. After enabling Developer Mode, there should be a new button at the bottom labelled *Add dev addon....* Click this button. A dialog will appear asking for the URL to the addon's `addon.json` file on your local web server. Enter its path, e.g. `http://localhost:65432/myaddon/addon.json`, and press OK. If the `addon.json` file is reachable and parsed successfully, you'll see a message indicating to restart Construct 3 to load the addon. If an error occurs, check the browser console for more details.

Step 5: develop the addon

Now every time you reload Construct 3, the latest version of your addon is loaded from the local web server. This makes it much quicker to test changes to your addon. For example if you make a change that crashes Construct 3 on startup, there is no need to clear the browser cache to remove the addon; you can simply fix the problem and reload C3.

Your addon will appear in the Addon Manager as having a "Developer" source. Note "Developer" addons cannot be bundled with projects when using the *Bundle addons* feature.

You can also uninstall your developer mode addon like any other addon, by right-clicking it in the Addon Manager and selecting *Uninstall*.

SAFE MODE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/guide/safe-mode>

For normal addon development, you should use [addon testing mode](#). This allows quick iteration and you can easily fix addons even if they crash Construct 3 on startup. However in some cases you may build a .c3addon package which accidentally still crashes the editor on startup. To remove this addon, you can clear your browser storage. Alternatively you can use Safe Mode in Construct 3, which does not load third-party addons but still lists them in the Addon Manager so they can be uninstalled.

To use Safe Mode, add ?safe-mode to the URL, e.g. [editor.construct.net/?safe-mode](#). Note all third-party addons are disabled in this mode. You should immediately open the Addon Manager, uninstall the problematic addon, and then restart Construct 3. Be sure to remove the ?safe-mode part of the URL to re-enable loading third-party addons.

It is not recommended to open any projects or try to do any actual work in safe mode: it exists only so you can reach the Addon Manager dialog to uninstall the addon.

TIMELINE INTEGRATION

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/guide/timeline-integration>

Adding [timeline](#) support to a 3rd party addon, be it a [plugin](#), [behavior](#) or [effect](#) is quite easy. A little bit of extra work is needed though, here is how to do it.

Plugins

- 1 Set the interpolatable [plugin property](#) option to true in all the plugin properties which should be supported by timelines.
- 2 Implement the `GetPropertyValueByIndex(index)` method in the plugin instance class.

index argument

Refers to the index of each property in the plugin as they are given to the constructor of the plugin instance class.

return value

The current value associated with the passed in index. Depending on the current implementation this could be as easy as returning an existing variable.

Colors: color properties should be returned as an array of 3 values. If the internal representation used by the plugin is different, the conversion needs to be made before returning the color.

Angles: if a plugin uses a value as an angle, but it is not specifically defined as an angle in the plugin definition, this method needs to make sure the value is in the same format as it is shown in the editor before returning it. Ex. A plugin internally converting a property from degrees to radians, should make sure the value returned by `GetPropertyValueByIndex` is in degrees.

- 3 Implement the `SetPropertyValueByIndex(index, value)` method in the plugin instance class.

index argument

Refers to the index of each property in the plugin as they are given to the constructor of the plugin instance class.

value argument

The new value that needs to be applied to the specified property. The passed ir value is absolute so it should be applied directly with the = operator.

return value

No return value is required.

Depending on the implementation, additional work might be needed when a property changes. Ex. If the plugin relies on any sort of caching relating to a property, changing that property would require an update to the cache in order for everything to continue working properly as the plugin is modified by a timeline.

Colors: these values are received as arrays of 3 values. The values should be applied according to the plugin's internal representation.

Angles: if a plugin uses a value as an angle, but it is not specifically defined as angle in the plugin definition. This method needs to make sure the incoming value is using the same format as the internal representation before making the assignment. Ex. A plugin internally converting a property from degrees to radians, will need to convert the incoming value of SetPropertyValueByIndex from degrees into radians.

Behaviors

See plugin integration above, all steps apply.

Effects

Edit the effect's .json file and add the interpolatable property with a value of true to each [parameter definition](#) which should be supported by timelines. No additional modifications needed.

NOTE: Remember that not all properties need to be supported, if it looks like it doesn't make sense for a property to receive dynamic updates, it is ok to not support it.

IBEHAVIORINSTANCEBASE INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/base-classes/ibehaviorinstancebase>

The `IBehaviorInstanceBase` interface is used as the base class for behavior instances in the SDK.

`IBehaviorInstanceBase` cannot be directly constructed; it should only be used as a base class.

Properties

this._sdkBehaviorType

Reference to the associated SDK type class.

this._behaviorInstance

Reference to the [IBehaviorInstance](#) interface representing this instance in the editor. This allows access to Construct's built-in features for behavior instances.

Methods

OnPropertyChanged(id, value)

Optional override for when a property with the given ID is changed. The value the property was changed to is also passed.

GetBehaviorInstance()

Return the [IBehaviorInstance](#) interface representing this instance in the editor.

GetSdkBehaviorType()

Return the associated SDK type class.

IINSTANCEBASE INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/base-classes/iinstancebase>

The `IInstanceBase` interface is used as the base class for instances in the SDK. For "world" type plugins, instances instead derive from [IWorldInstanceBase](#), which itself derives from `IInstanceBase`.

`IInstanceBase` cannot be directly constructed; it should only be used as a base class.

Properties

`this._sdkType`

Reference to the associated SDK type class.

`this._inst`

Reference to the [IObjectInstance](#) interface, or [IWorldInstance](#) interface for "world" type plugins, representing this instance in the editor. This allows access to Construct's built-in features for instances.

Methods

`Release()`

Optional override for when an instance is released.

`OnCreate()`

Optional override for when an instance is created in the editor.

`OnPropertyChanged(id, value)`

Optional override for when a property with the given ID is changed. The value the property was changed to is also passed.

`LoadC2Property(name, valueString)`

Optional override to use custom logic for importing properties from a Construct 2 project referencing a Construct 2 version of this plugin.

`GetProject()`

Return the [IProject](#) representing the instance's associated project.

GetObjectType()

Convenience method to return the [IObjectType](#) interface representing Construct's object type class.

GetInstance()

Return the [IObjectInstance](#) corresponding to this instance.

IWORLDINSTANCEBASE INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/base-classes/iworldinstancebase>

The `IWorldInstanceBase` interface is used as the base class for instances in the SDK for "world" type plugins. It derives from [IInstanceBase](#).

`IWorldInstanceBase` cannot be directly constructed; it should only be used as a base class.

Methods

OnPlacedInLayout()

Optional override called when an instance is explicitly placed in the layout by the user. This is the right time to set any additional defaults such as the initial size or origin.

Draw(iRenderer, iDrawParams)

Called when Construct wants the instance to draw itself in the Layout View.

`iRenderer` is an [IWebGLRenderer](#) interface, used for issuing draw commands. `iDrawParams` is an [IDrawParams](#) interface, used for providing additional information to the draw call.

GetTexture(animationFrame)

Load a texture from an [IAnimationFrame](#). Texture loading is asynchronous and is started in the first call. The method will return `null` while the texture is loading. Construct will automatically refresh the Layout View when the texture finishes loading, at which point the method will return an [IWebGLTexture](#) interface that can be used for rendering. Plugins typically render a placeholder of a semitransparent solid color while the texture is loading.

GetTexRect()

When a texture has successfully loaded, returns an [SDK.Rect](#) indicating the dimensions of the image to render in texture co-ordinates. Note that due to Construct's in-editor spritesheeting engine, this is usually a subset of a texture.

HadTextureError()

Returns true to indicate texture loading failed. Plugins typically switch the placeholder to a red color in this circumstance.

IsOriginalSizeKnown()

GetOriginalWidth()

GetOriginalHeight()

Optional overrides to specify the "original size" of the instance. Typically if a plugin supports this, it is the size of the image. This enables percentage size options in the Properties Bar. The default implementation returns `false` from `IsOriginalSizeKnown()`, disabling the feature. To enable it, return `true` from `IsOriginalSizeKnown()`, and return the original size in the `GetOriginalWidth()` and `GetOriginalHeight()` methods.

HasDoubleTapHandler()

OnDoubleTap()

Optional override which is called when the user double-clicks or double-taps an instance in the Layout View. This also enables an *Edit* option in the context menu, which also calls the double-tap handler. Typically plugins with an image use this handler to edit the image. The default implementation returns `false` from `HasDoubleTapHandler()`, disabling the feature. To enable it, return `true` from `HasDoubleTapHandler()` and then override `OnDoubleTap()` to perform a task.

COLOR INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/geometry-interfaces/color>

The `Color` interface represents a floating-point RGBA color in the SDK. It can also be constructed independently as a general-purpose color class. Each color component is normalized to the range [0, 1].

In the WebGL renderer, colors are normally required to have premultiplied alpha. Some APIs already return premultiplied colors, but others may not; check the documentation for any API methods returning colors to find out which are used. Wherever possible avoid using the `unpremultiply()` method, since it is lossy.

Constructor

```
new SDK.Color();  
new SDK.Color(r, g, b, a);
```

A `Color` can be constructed with no parameters, which defaults all components to zero, or with given RGBA components.

Methods

setRgb(r, g, b)

Set the RGB components only, without affecting the alpha component, in a single call.

setRgba(r, g, b, a)

Set the RGBA components of the color in a single call.

copy(color)

Set the components of the color by copying another `SDK.Color`.

copyRgb(color)

Set the RGB components only, without affecting the alpha component, by copying another `SDK.Color`.

clone()

Return a new instance of an `SDK.Color` with an identical color to this one.

setR(r)

setG(g)

setB(b)

setA(a)

Set each component of the color individually. Note color components are floats in the range [0, 1].

getR()

getG()

getB()

getA()

Get each component of the color individually.

equals(color)

Return a boolean indicating if this color exactly matches another

`SDK.Color`.

equalsIgnoringAlpha(color)

Return a boolean indicating if this color exactly matches the RGB components of another `SDK.Color`. The alpha component is ignored.

equalsRgb(r, g, b)

Return a boolean indicating if this color exactly matches the given RGB components.

equalsRgba(r, g, b, a)

Return a boolean indicating if this color exactly matches the given RGBA components.

premultiply()

Multiply the RGB components by the A component. This is usually required for rendering.

unpremultiply()

Divide the RGB components by the A component.

*Avoid this method whenever possible, because it is lossy.
(Unpremultiplying a premultiplied color will lose some precision in the RGB components and may not exactly match the original color.)*

QUAD INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/geometry-interfaces/quad>

The `Quad` interface represents a shape made from four points in the SDK. Typically it is used to represent rotated rectangles. It is also the main primitive used for rendering, by passing object's bounding quads to the WebGL renderer.

Constructor

```
new SDK.Quad();  
new SDK.Quad(tlx, tly, trx, try_, brx, bry, blx, bly);
```

A `Quad` can be constructed with no parameters, which defaults all co-ordinates to zero, or with given positions for each point. The naming convention is tl for the "top-left" point, tr for the "top-right" point, br for the "bottom-right" point, and bl for the "bottom-left" point, followed by "x" or "y" for each component of the point. Note that the points can appear at any orientation for rotated quads; the names only correspond to their actual position when the quad is set to an unrotated rectangle.

The name `try` is a keyword in JavaScript, so the "top-right Y" component is named with an underscore as `try_` to avoid colliding with the keyword.

Methods

set(tlx, tly, trx, try_, brx, bry, blx, bly)

Set all four points of the quad in a single call.

setRect(left, top, right, bottom)

Set the quad's points to represent an axis-aligned rectangle using the given positions. Note that this is only useful if you subsequently make further modifications to the quad, else you may as well use the [Rect](#) interface.

copy(quad)

Set all points of the quad by copying another `SDK.Quad`.

setTlx(n)

setTly(n)

setTrx(n)

setTry(n)
setBrx(n)
setBry(n)
setBlx(n)
setBly(n)

Set each point of the quad individually.

getTlx()
getTly()
getTrx()
getTry()
getBrx()
getBry()
getBlx()
getBly()

Get each point of the quad individually.

setFromRect(rect)

Set the points of the quad to an axis-aligned rectangle given by an [SDK.Rect](#). Note that this is only useful if you subsequently make further modifications to the quad, else you may as well use the Rect interface directly.

setFromRotatedRect(rect, angle)

Set the points of the quad to a rotated rectangle given by an [SDK.Rect](#), rotated about the origin by `angle` in radians.

getBoundingBox(rect)

Calculate the bounding box of the quad, and store the result by writing to a given [SDK.Rect](#).

midX()

midY()

Return the average of the four points in the quad on each axis.

intersectsSegment(x1, y1, x2, y2)

Test if a segment, given as the line between points (x1, y1) and (x2, y2), intersects this quad, returning a boolean.

intersectsQuad(quad)

Test if another SDK.Quad intersects this quad, returning a boolean.

containsPoint(x, y)

Test if the given point is inside the bounds of this quad, returning a boolean.

RECT INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/geometry-interfaces/rect>

The `Rect` interface represents an axis-aligned rectangle in the SDK. It can also be constructed independently as a general-purpose geometry class.

Constructor

```
new SDK.Rect();  
new SDK.Rect(left, top, right, bottom);
```

A `Rect` can be constructed with no parameters, which defaults all co-ordinates to zero, or with given positions for the left, top, right and bottom positions.

Methods

set(left, top, right, bottom)

Set all sides of the rectangle in one call.

copy(rect)

Set all sides of the rectangle by copying another `SDK.Rect`.

clone()

Return a new instance of an `SDK.Rect` with identical values to this one.

setLeft(left)

setTop(top)

setRight(right)

setBottom(bottom)

Set the position of each side of the rectangle individually.

getLeft()

getTop()

getRight()

getBottom()

Get the position of each side of the rectangle individually.

width()

height()

Get the width or height of the rectangle. Note if the right edge is to the left of the left edge, or the bottom edge above the top edge, this will return a negative size.

midX()

midY()

Return the average of the left and right, or top and bottom, positions.

offset(x, y)

Add `x` to the left and right positions, and `y` to the top and bottom positions, offsetting the entire rectangle.

inflate(x, y)

deflate(x, y)

Expand or shrink the rectangle using the given offsets. Inflating subtracts from the left and top edges and adds to the right and bottom edges, and deflating does the opposite.

multiply(x, y)

divide(x, y)

Multiply or divide each position by a given factor on each axis.

clamp(left, top, right, bottom)

Clamp each position in the rectangle to a given value, ensuring the rectangle does not extend beyond the bounds of the passed rectangle.

normalize()

Normalize the rectangle positions, swapping the left-right positions if the right position is on the left, and swapping the top-bottom positions if the bottom position is on the top. This ensures the width and height are positive.

intersectsRect(rect)

Test for an intersection with another `SDK.Rect`, returning a boolean indicating if it intersects.

containsPoint(x, y)

Test if the given point is inside the bounds of this rectangle, returning a boolean.

IDRAWPARAMS INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/graphics-interfaces/idrawparams>

The `IDrawParams` interface provides additional parameters to a `Draw()` call in the SDK.

This interface cannot be directly constructed. It is only available in the `Draw()` call.

Methods

GetDt()

Return delta-time, the time since the last frame, in seconds. This is typically approximately 1/60th of a second (0.01666...). This value is only valid when the Layout View is continually scrolling, such as when dragging an instance to the edge of the Layout View window. Any other time it will be set to a dummy non-zero value, since there wasn't a frame immediately preceding the current one.

GetLayoutView()

Return an [ILayoutView](#) interface representing the current Layout View being drawn. This allows access to features of the Layout View in drawing code.

IWEBGLRENDERER INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/graphics-interfaces/iwebglrenderer>

The `IWebGLRenderer` interface provides methods for rendering to the Layout View, which is rendered using a WebGL canvas. The interface's methods provide high-level drawing commands implemented by Construct, so you don't need to handle low-level concerns like vertex buffers.

This interface cannot be directly constructed. It is only available as a parameter to a `Draw()` call.

Renderer state

Since `IWebGLRenderer` is based on WebGL, it also uses a persistent rendering state. Therefore to correctly render something, all the intended state must be specified, otherwise it will use an undefined previous state. `IWebGLRenderer` simplifies the renderer state to:

- 1 A blend mode. Typically a normal alpha blend mode is used.
- 2 A fill mode (internally, the current fragment shader). The fill modes can be *color fill* (draw a solid color), *texture fill* (draw a texture), and *smooth line fill* (for drawing smooth lines).
- 3 A color set by `SetColor()` or `SetColorRgba()`. The alpha component of the color is used as the opacity in texture fill mode.
- 4 A texture set by `SetTexture()`. This is only used in texture fill mode.

Therefore a `Draw()` method should begin by specifying the blend mode, the fill mode, the color, and the texture (if texture fill mode is used), before continuing to draw. The renderer efficiently discards redundant calls, so if the state does not actually change then these calls have minimal performance overhead.

Once all state is set up, quads can be issued using one of the `Rect()` or `Quad()` method overloads. These methods draw using the currently set state.

Methods

`SetAlphaBlendMode()`

Set the blend mode to a premultiplied alpha blending mode.

SetColorFillMode()

Set the fill mode to draw a solid color, specified by the current color.

SetTextureFillMode()

Set the fill mode to draw a texture, specified by the current texture, and using the alpha component of the current color as the opacity.

SetSmoothLineFillMode()

Set the fill mode to draw smooth lines using the current color.

SetColor(color)

Set the current color with an [SDK.Color](#).

SetColorRgba(r, g, b, a)

Set the current color by directly passing the RGBA components.

SetOpacity(o)

Set only the alpha component of the current color. Note this does not affect the RGB components.

SetCurrentZ(z)

GetCurrentZ()

Set and get the current Z component used for all 2D drawing commands that don't specify Z components, such as the `Rect2()` and `Quad3()`.

ResetColor()

Set the current color to (1, 1, 1, 1).

Rect(rect)

Draw a rectangle given by an [SDK.Rect](#).

Rect2(left, top, right, bottom)

Draw a rectangle by directly passing the left, top, right and bottom positions.

Quad(quad)

Draw a quad given by an [SDK.Quad](#).

Quad2(tlx, tly, trx, try_, brx, bry, blx, bly)

Draw a quad by directly passing the positions of each of the four points in the quad.

Quad3(quad, rect)

Draw a quad given by an [SDK.Quad](#), using an [SDK.Rect](#) for the source texture co-ordinates to draw from.

Quad4(quad, texQuad)

Draw a quad given by an [SDK.Quad](#), using another `SDK.Quad` for the source texture co-ordinates to draw from.

Quad3D(tlx, tly, tlz, trx, try_, trz, brx, bry, brz, blx, bly, blz, rect)

Quad3D2(tlx, tly, tlz, trx, try_, trz, brx, bry, brz, blx, bly, blz, texQuad)

Draw a 3D quad, specifying all four points of the quad with X, Y and Z co-ordinates. The first overload accepts texture co-ordinates via an [SDK.Rect](#) *rect*, and the second accepts texture co-ordinates via an [SDK.Quad](#) *texQuad*.

ConvexPoly(pointsArray)

Draw a convex polygon using the given array of points, in alternating X, Y order. Therefore the size of the array must be even, and must contain at least six elements (to define three points).

Line(x1, y1, x2, y2)

Draws a quad from the point (x1, y1) to (x2, y2) with the current line width.

TexturedLine(x1, y1, x2, y2, u, v)

Draws a quad from the point (x1, y1) to (x2, y2) with the current line width, and using (u, 0) as the texture co-ordinates at the start, and (v, 0) as the texture co-ordinates at the end.

LineRect(left, top, right, bottom)

Draws four lines along the edges of a given rectangle.

LineRect2(rect)

Draws four lines along the edges of a given `SDK.Rect`.

LineQuad(quad)

Draws four lines along the edges of a given `SDK.Quad`.

PushLineWidth(w)

PopLineWidth()

Set the current line width for line-drawing calls. This must be followed by a `PopLineWidth()` call when finished to restore the previous line width.

PushLineCap(lineCap)

PopLineCap()

Set the current line cap for line-drawing calls. This must be followed by a `PopLineCap()` call when finished to restore the previous line cap. The available line caps are `"butt"` and `"square"`.

SetTexture(texture)

Set the current texture to a given [IWebGLTexture](#).

CreateWebGLText()

Return a new [IWebGLText](#) interface. This manages text wrapping, drawing text, and uploading the results to a WebGL texture.

CreateDynamicTexture(width, height, opts)

Create a new empty [IWebGLTexture](#) for dynamic use, i.e. expecting the texture content to be replaced using `UpdateTexture()`. The size of the texture is given by `width` and `height` which must be positive integers. `opts` specifies options for the texture which is an object that can include the following properties:

- `wrapX`: the texture horizontal wrap mode: one of `"clamp-to-edge"`, `"repeat"`, `"mirror-repeat"`
 - `wrapY`: as with `wrapX` but for the vertical wrap mode
 - `sampling`: the texture sampling mode, one of `"nearest"`, `"bilinear"` or `"trilinear"` (default)
 - `pixelFormat`: the texture pixel format, one of `"rgba8"` (default), `"rgb8"`, `"rgba4"`, `"rgb5_a1"` or `"rgb565"`
 - `mipMap`: boolean indicating if mipmaps should be used for this texture, default true
 - `mipMapQuality`: if `mipMap` is true, one of `"default"` (default), `"low"` or `"high"`
-

UpdateTexture(data, texture, opts)

Upload *data* as the new texture contents for the [IWebGLTexture](#) *texture*. This can only be used for textures created with `CreateDynamicTexture()` and managed by your addon.

data can be one of the following types: `HTMLImageElement`, `HTMLVideoElement`, `HTMLCanvasElement`, `ImageBitmap`, `OffscreenCanvas` or `ImageData`. Note in worker mode the DOM types cannot be used (`HTMLImageElement`, `HTMLVideoElement`, `HTMLCanvasElement`); in this case use `ImageBitmap` or `OffscreenCanvas` instead. This method cannot resize an existing texture, so the data must match the size the texture was created with; if the size needs to change, destroy and re-create the texture.

opts specifies options for the texture upload which is an object that can include the following properties:

- `premultiplyAlpha`: a boolean indicating whether to premultiply alpha of the image content specified by *data* (default true). Construct always renders using premultiplied alpha so this is normally necessary; however if the data is known to already be premultiplied, set this to false.

DeleteTexture(texture)

Delete a [IWebGLTexture](#), releasing its resources. This can only be used for textures created with `CreateDynamicTexture()` and managed by your addon. Do not attempt to delete textures managed by the Construct engine.

IWEBGLTEXT INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/graphics-interfaces/iwebgltext>

The `IWebGLText` interface manages text wrapping, drawing text to a canvas, and then uploading the result to a WebGL texture. This makes it easy to display text in a WebGL renderer. It is created via the [IWebGLRenderer](#)

`CreateWebGLText()` method.

Methods

Release()

Destroy the object and its resources. `IWebGLText` must be released when it is no longer needed; do not simply drop references, otherwise not all of its resources will be collected. If your plugin creates an `IWebGLText`, it should release any it still uses in its own `Release()` method.

SetFontName(name)

Set the name of the font face used for drawing text.

SetFontSize(ptSize)

Set the size of the font, in points, used for drawing text.

SetLineHeight(px)

Set the extra line height spacing, in pixels, used for drawing text. Note 0 is the default, indicating no offset to the default line height.

SetBold(b)

Set the bold flag used for drawing text.

SetItalic(i)

Set the italic flag used for drawing text.

SetColor(color)

Set the color of the text using a [SDK.Color](#) or a string. If a string is passed, it is passed directly to a 2D canvas `fillStyle` property, so can be anything that property accepts, e.g. "red", "#00ffee", "rgb(0, 128, 192)" etc.

SetColorRgb(r, g, b)

Set the color of the text using separate RGB components.

SetHorizontalAlignment(h)

Set the horizontal alignment of the text within its bounding box. This can be one of `"left"`, `"center"` or `"right"`.

SetVerticalAlignment(v)

Set the vertical alignment of the text within its bounding box. This can be one of `"top"`, `"center"` or `"bottom"`.

SetWordWrapMode(m)

Set the word wrapping mode. This can be one of `"word"` (for space-delimited word wrapping) or `"character"` (for wrapping on any character).

SetText(text)

Set the text string to be drawn.

SetSize(width, height, zoomScale)

Set the size of the area that text can be drawn in. The size is specified in CSS pixels. The `zoomScale` can be increased to render the text at a higher resolution, which is useful when zooming in the Layout View.

GetTexture()

Get an [IWebGLTexture](#) interface representing the texture with the requested text rendered on to it. Note: the texture is generated asynchronously, so can return `null` when first requested. Use `SetTextureUpdateCallback()` to get a callback when the texture has updated, where the relevant Layout View can be redrawn to render with the updated texture.

GetTexRect()

Return a [SDK.Rect](#) representing the content area of the text on the WebGL texture. This is the subset of the texture that ought to be rendered. Note: this is only valid when `GetTexture()` returns a non-null result.

SetTextureUpdateCallback(callback)

Set a function to call when the texture containing the rendered text is updated. Since the texture is generated asynchronously, this is necessary to know when to redraw any views that may be displaying the text, so they can redraw with the updated texture.

ReleaseTexture()

Release the underlying WebGL texture. This can be used to save memory. However the texture will be re-created the next time `GetTexture()` is called.

GetTextWidth()**GetTextHeight()**

Return the size of the text bounding box after processing word wrap. This allows determining the size of the actual visible text, rather than the box used for word wrap bounds.

IWEBGLTEXTURE INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/graphics-interfaces/iwebgltexture>

The `IWebGLTexture` interface represents a texture in the WebGL renderer.

This interface cannot be directly constructed. It is only available through other APIs.

Methods

GetWidth()

GetHeight()

Return the width or height of the texture. Note this refers to the source texture. Construct's in-editor spritesheeting engine means the texture could be significantly larger than an object's image to be rendered from it.

ILANG INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/misc-interfaces/ilang>

The `ILang` interface allows for looking up translated strings in the language file.

Only look up language strings from your own addon. Any other strings in the language file are subject to change at any time.

Methods

PushContext(prefix)

Push a prefix to the context stack. For example `PushContext("foo")` followed by `Get(".bar")` will return the same string as if `Get("foo.bar")` were used. Pushing a context beginning with a dot will append to the current prefix, but pushing an entry not beginning with a dot will reset the current prefix. Note: be sure to always call `PopContext()` afterwards.

PopContext()

Pop a prefix from the context stack.

Get(context)

Look up a string in the language file. If the context begins with a dot, it is relative to the current context prefix. Otherwise it is treated as an absolute context.

For convenience Construct also adds this method as a global function

```
self.lang()
```

IZIPFILE INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/misc-interfaces/zipfile>

The `IZipFile` interface represents a zip file in the SDK. It allows access to the file list and reading files contained within the zip.

Methods

PathExists(path)

Return a boolean indicating if a given path exists within the zip.

GetFileList()

Return an array of all file paths contained within the zip.

GetFirstEntryWithExtension(ext)

Return a [IZipFileEntry](#) representing the first entry found with a given file extension, or `null` if none was found.

GetEntry(path)

Return a [IZipFileEntry](#) representing the file at the given path. If the path does not exist in the zip, this returns `null`.

ReadText(entry)

Return a promise that resolves with the contents of the given [IZipFileEntry](#) read as plain text.

ReadJson(entry)

Return a promise that resolves with the contents of the given [IZipFileEntry](#), read as plain text and then parsed as JSON.

ReadBlob(entry)

Return a promise that resolves with the contents of the given [IZipFileEntry](#), read as a `Blob`. (This is a raw binary format that can be read with other JavaScript APIs.)

The returned blob will have `name` and `lastModified` properties added, reflecting the properties of the file in the zip.

IZIPFILEENTRY INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/misc-interfaces/zipfileentry>

The `IZipFileEntry` interface is an opaque reference to an file entry in [IZipFile](#). It has no methods - instead, simply pass it to one of the other methods in `IZipFile`.

IEVENTBLOCK INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/model-interfaces/ieventblock>

The `IEventBlock` interface represents an event block in the event sheet. Event blocks are the most important kind of event, and consist of a number of conditions, actions to run when the conditions are met, and optionally further sub-events. It derives from [IEventParentRow](#).

Creating an event block

The following code sample demonstrates the calls necessary to add an *On start of layout* event to the associated event sheet for a given [ILayoutView](#). This is useful with the Custom Importer API, since the [AddDragDropFileImporterHandler](#) callback provides the `ILayoutView` that content was dropped in to.

```
// Note: this code is assumed to be in an async function
// First get the associated event sheet for the layout view
const eventSheet = layoutView.GetLayout().GetEventSheet();
if (eventSheet) // note the layout may not have an event sheet
{
    // Get the IObjectType for the System plugin
    const systemType = eventSheet.GetProject().GetSystemType();

    // Create an empty event block at the root level of the event sheet
    const eventBlock = await eventSheet.GetRoot().AddEventBlock();

    // Add an 'On start of layout' condition
    eventBlock.AddCondition(systemType, null, "on-start-of-layout");

    // Example code for adding a 'Set position' action
    //eventBlock.AddAction(iObjectType, null, "set-position", [100, 200]);
}
```

Finding condition and action IDs

Some developer methods are available to explore the list of condition and action

IDs that can be used to create events with. See [Finding addon IDs](#) for more information.

Methods

AddCondition(iObjectClass, reserved, cndId, params)

AddAction(iObjectClass, reserved, actId, params)

Add a condition or action to this event block. These methods are very similar so they are documented together. *iObjectClass* must be an [IObjectClass](#) (i.e. an [IObjectType](#) or [IFamily](#)) to create the condition and action for. The next parameter is reserved for future use; you must pass `null`. *cndId* or *actId* must be a string specifying the condition or action to create; for example the System *On start of layout* condition ID is `"on-start-of-layout"`. If the condition or action uses any parameters, then *params* must be an array with enough elements for every parameter. Each parameter can be a string, number or IObjectType. Expression parameters use a string, which can be any valid expression (including calculations like `"1+1"` for number parameters); if you pass a number, it will be converted to a string. IObjectClass can also be passed for object parameters.

IEVENTPARENTROW INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/model-interfaces/ieventparentrow>

The `IEventParentRow` interface is a base class representing any row in the event sheet that can have other events nested beneath it. For example an event group is a parent row since it can have other events nested inside it, but an event comment is not a parent row, because nothing can be nested inside it. Note that the root node of the event sheet is a parent row.

Methods

async AddEventBlock()

Add an empty child event block, with no conditions or actions. Returns a promise resolving with the created [IEventBlock](#).

IEVENTSHEET INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/model-interfaces/ieventsheetsheet>

The `IEventSheet` interface represents an event sheet in the project model.

Since events can be nested underneath each other, they are represented as a tree. `GetRoot()` returns the root node of the tree.

Methods

GetProject()

Return the associated [IProject](#).

GetName()

Return the name of the event sheet.

GetRoot()

Return the root node of the event sheet. This is an [IEventParentRow](#) representing the top level of the event sheet.

ILAYER INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/model-interfaces/ilayer>

The `ILayer` interface represents a layer in the project model.

Methods

GetName()

Return the name of the layer.

GetLayout()

Return the [ILayout](#) this layer belongs to.

ILAYOUT INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/model-interfaces/ilayout>

The `ILayout` interface represents a layout in the project model. Note that [ILayoutView](#) represents the editor view, but `ILayout` represents the layout in the project.

Methods

GetProject()

Return the associated [IProject](#).

GetName()

Return the name of the layout.

GetAllLayers()

Return an array of [ILayer](#) representing all the layers on this layout.

GetEventSheet()

Return the [IEventSheet](#) assigned for this layout. Note that layouts do not have to have an event sheet assigned, so this can return `null`.

IPROJECT INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/model-interfaces/iproject>

The `IProject` interface provides access to a project from the SDK.

Methods

GetName()

Return the project name.

GetRuntime()

Return the runtime the project is set to use - either `"c2"` for the legacy C2 runtime or `"c3"` for the modern C3 runtime.

GetObjectTypeByName(name)

GetFamilyByName(name)

GetObjectClassByName(name)

Look up an object class by a case-insensitive string of its name, returning either an [IObjectType](#) (for *GetObjectTypeByName*), an [IFamily](#) (for *GetFamilyByName*), or either (for *GetObjectClassByName*), or `null` if not found.

CreateObjectType(pluginId, name)

Add a new object type to the project. Returns a promise that resolves with an [IObjectType](#) representing the new object type. See [Finding addon IDs](#) to get a list of possible plugin IDs that can be used. `name` is the requested name to use for the object type. If the name is free, it will be used directly; however if the name is already in use, Construct will change the name to one which is available. Call `GetName()` on the returned [IObjectType](#) to determine what name it was assigned.

GetSystemType()

Return an [IObjectType](#) representing the System plugin, which exists in every project.

GetSingleGlobalObjectType(pluginId)

Return an [IObjectType](#) representing a single-global plugin in the project. Returns `null` if the given plugin ID does not exist, is not a single-global plugin, or the plugin has not been added to the project. See [Finding addon IDs](#)

to get a list of possible plugin IDs that can be used.

CreateFamily(name, members)

Create a new family in the project. *name* is an optional family name (pass `null` to use a default name). *members* must be an array of [IObjectType](#) representing the object types to add to the family. Families must be created with at least one object type, and if they have multiple object types, they must all be from the same kind of plugin (e.g. all Sprites). Returns an [IFamily](#) representing the created family.

GetProjectFileByName(name)

Look up a project file by a case-insensitive string of its filename, returning an [IProjectFile](#) if found, else `null`.

AddOrReplaceProjectFile(blob, filename, kind = "general")

Create a new project file in the project, or replace the content of the file if it already exists, using a `Blob` for the file content and a string for the filename. The *kind* defaults to `"general"`, which causes the file to be placed in the "Files" folder in the Project Bar. Other options are `"sound"`, `"music"`, `"video"`, `"font"` and `"icon"`.

ShowImportAudioDialog(fileList)

Bring up the *Import audio* dialog to import a list of audio files given in `fileList`. This will automatically transcode the audio files to WebM Opus (when supported for the audio formats), which is the main format Construct uses. Prefer importing PCM WAV files to ensure transcoding is supported and is lossless. The file list should be an array of `Blob` or `File`; if blobs, then ensure a `name` property is assigned to the blob object to indicate the intended filename.

Reading blobs from [IZipFile](#) automatically assigns a name property so the blobs can be directly passed to this method.

EnsureFontLoaded(f)

Make sure a given font name is loaded so it can be used when drawing text. This is necessary for plugins that render text.

UndoPointChangeObjectInstancesProperty(instances, propertyId)

Create a new undo point that undoes changes to `propertyId`. `instances` must be either an [IObjectInstance](#) or an array of [IObjectInstance](#). Call this method before changing an instance's property value and the action will be undoable.

IPROJECTFILE INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/model-interfaces/iprojectfile>

The `IProjectFile` interface represents a project file added in the Project Bar in Construct.

Methods

GetName()

Return the filename of the project file.

GetProject()

Return the [IProject](#) the project file belongs to.

GetBlob()

Return a [Blob](#) representing the contents of the file. The standard web APIs for reading blobs can be used to access the content.

IAnimation Interface

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/object-interfaces/ianimation>

The `IAnimation` interface represents an animation within an animated object type. This is only applicable to animated plugins such as Sprite.

Methods

GetObjectType()

Return the [IObjectType](#) that this animation belongs to.

GetFrames()

Return an array of [IAnimationFrame](#) representing the frames in this animation.

AddFrame(blob, width, height)

Add a new animation frame to the animation. All the parameters are optional. There are four overloads of this method:

- 1 No parameters passed: add an empty animation frame with a default size
- 2 Blob passed with no size: use the blob as the animation frame image file, and decompress the image to determine the size
- 3 Blob passed with size: use the blob as the animation frame image file and use the provided size (which must be correct) to skip having to decompress the image to find its size
- 4 No blob passed but size provided: use the size for the empty animation frame

The method returns a promise that resolves with the added [IAnimationFrame](#).

SetSpeed(s)

GetSpeed()

Set and get the animation speed in animation frames per second.

SetLooping(l)

IsLooping()

Set and get the looping flag for the animation, indicating if the animation will repeat.

SetPingPong(p)

IsPingPong()

Set and get the ping-pong flag for the animation, indicating if the animation will repeat alternating forwards and backwards.

SetRepeatCount(r)

GetRepeatCount()

Set and get the number of times the animation is set to repeat.

SetRepeatTo(f)

GetRepeatTo()

Set and get the animation frame index to return to when repeating the animation. This must be a valid index.

Delete()

Immediately deletes this animation from its object without any confirmation prompt. This cannot be undone.

The last animation is not allowed to be deleted. Construct requires that animated objects have at least one animation.

Use this with care as it does not warn the user and cannot be undone.

IAnimationFrame Interface

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/object-interfaces/ianimationframe>

The `IAnimationFrame` interface represents an image for an object type. Despite the name, this interface is also used if the plugin uses a single image, like Tiled Background does.

Note `IAnimationFrame` cannot be directly rendered. You must first create a texture from it.

This interface provides methods for loading a texture, but you don't normally need to use them. Simply pass the `IAnimationFrame` to [WorldInstanceBase's](#) `GetTexture()` method, which provides a default implementation using these methods.

Methods

GetObjectType()

Return the associated [ObjectType](#) interface.

GetWidth()

GetHeight()

Return the size of the image, in pixels.

GetCachedWebGLTexture()

Return an [IWebGLTexture](#) interface if the texture is already loaded, else `null`.

GetTexRect()

Return an [SDK.Rect](#) representing the texture co-ordinates of this image on the loaded texture. This can only be called if `GetCachedWebGLTexture()` returned a texture.

LoadWebGLTexture()

Start asynchronously loading a texture for this image. This should only be used if `GetCachedWebGLTexture()` returned `null`.

ReplaceBlobAndDecode(blob)

Replace the image content of the animation frame with the given blob. The blob will be decoded as an image and the previous content of the animation frame overwritten with the image content of the blob. This may also change the size of the frame. Returns a promise that resolves when the image content has been updated.

SetDuration(d)

GetDuration()

Set and get the individual frame duration. This is a multiplier, e.g. 1 for normal speed, 2 for twice as long, etc.

SetOriginX(x)

SetOriginY(y)

GetOriginX()

GetOriginY()

Set and get the origin for this image. The origin is specified in texture coordinates, i.e. from 0 to 1. The default is 0.5, indicating the middle of the image.

GetImagePoints()

Return an array of [IImagePoint](#) representing the image points added to the image.

AddImagePoint(name, x, y)

Add a new image point to the image with the specified name and position. As with the origin, image point positions are specified in texture co-ordinates, i.e. from 0 to 1. Returns an [IImagePoint](#) representing the added image point.

GetCollisionPoly()

Return the [ICollisionPoly](#) representing the image's collision polygon.

Delete()

Immediately deletes this frame from its animation without any confirmation prompt. This cannot be undone.

The last frame is not allowed to be deleted. Construct requires that animations have at least one frame.

Use this with care as it does not warn the user and cannot be undone.

IBEHAVIORINSTANCE INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/object-interfaces/ibehaviorinstance>

The `IBehaviorInstance` interface represents a behavior instance in Construct.

Methods

GetProject()

Return the [IProject](#) representing the behavior instance's associated project.

GetPropertyValue(id)

Get the value of a behavior property for this behavior instance by its property ID.

SetPropertyValue(id, value)

Set the value of a behavior property for this instance by its property ID.

ICOLLISIONPOLY INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/object-interfaces/icollisionpoly>

The `ICollisionPoly` interface represents the collision polygon for an [AnimationFrame](#). It is represented as a list of numbers representing points connected in a loop. As with image points, the collision polygon points are specified in texture co-ordinates, i.e. from 0 to 1.

Methods

Reset()

Reset the collision polygon to the default, which matches the bounding box of the object.

IsDefault()

Return a boolean indicating if the collision polygon is set to the default, matching the bounding box of the object.

GetPoints()

Return an array of numbers representing the points in the collision polygon. The array elements are alternating X and Y components for the points, so its size is always even. The collision polygon is guaranteed to have at least three points.

SetPoints(arr)

Set the collision polygon points by passing an array of numbers. The array elements must be alternating X and Y components for the points, so its size must be even. There must be at least three points in a collision polygon, therefore the passed array must have at least 6 elements.

ICONTAINER INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/object-interfaces/container>

The `IContainer` interface represents a container in Construct, which is a group of object types that are always created, destroyed and picked together.

Methods

GetMembers()

Return an array of [IObjectType](#) representing the object types in the container. Containers always have at least two members.

SetSelectMode(m)

GetSelectMode()

Set or get the select mode of the container, corresponding to the *Select mode* property in Construct. Allowed modes are `"normal"`, `"all"` and `"wrap"`.

RemoveObjectType(objectType)

Remove a member [IObjectType](#) from this container.

A container must have at least two object types. If the second-last member is removed, the container becomes inactive and is effectively deleted. The last remaining member will also act as if it's no longer in a container.

IsActive()

Return a boolean indicating if the container is active. It becomes inactive if there are fewer than the minimum required two members, at which point it is effectively deleted.

IFAMILY INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/object-interfaces/ifamily>

The `IFamily` interface represents a family in Construct, which is a group of object types that can be treated as one. All object types in the family must be from the same plugin. It derives from [IObjectClass](#). Families can be created in the SDK using [IProject](#). `CreateFamily()` .

Methods

GetMembers()

Return an array of [IObjectType](#) representing the object types in the family.

SetMembers(objectTypes)

Set the members of the family by passing an array of [IObjectType](#). Note all the specified object types must be compatible with the family, including using the same plugin, and not having any naming conflicts between instance variables, behaviors and effects.

IIMAGEPOINT INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/object-interfaces/iimagepoint>

The `IImagePoint` interface represents an image point on an [IAnimationFrame](#).

Methods

GetAnimationFrame()

Return the associated [IAnimationFrame](#).

SetName(name)

GetName()

Set or get the name of the image point.

SetX(x)

SetY(y)

GetX()

GetY()

Set or get the position of the image point in texture co-ordinates, i.e. from 0 to 1.

IOBJECTCLASS INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/object-interfaces/iobjectclass>

The `IObjectClass` interface is the base class of [IObjectType](#) and [IFamily](#).

`IObjectClass` cannot be created directly. However any parameter that accepts an `IObjectClass` can accept any derivative, i.e. an object type or a family.

Methods

GetName()

Return the name of the object class.

GetProject()

Return the [IProject](#) representing the object class's associated project.

Delete()

Immediately deletes this object class from the project without any confirmation prompt. All events referencing it will also be removed. This cannot be undone.

Use this with care as it does not warn the user and cannot be undone.

IObjectInstance INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/object-interfaces/iobjectinstance>

The `IObjectInstance` interface represents an instance in Construct.

Methods

GetProject()

Return the [IProject](#) representing the instance's associated project.

GetObjectType()

Return the associated [IObjectType](#) interface for this instance.

GetUID()

Return the UID (unique ID) the editor has assigned to this instance.

GetPropertyValue(id)

Get the value of a plugin property for this instance by its property ID. Color properties return a [SDK.Color](#).

SetPropertyValue(id, value)

Set the value of a plugin property for this instance by its property ID. For color properties a [SDK.Color](#) must be passed as the value.

IObjectType INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/object-interfaces/iobjecttype>

The `IObjectType` interface represents an object type in Construct. It derives from [IObjectClass](#).

Methods

GetImage()

Return an [IAnimationFrame](#) representing the object type's image. The plugin must have specified `SetHasImage(true)` in [IPluginInfo](#).

EditImage()

Open the Animations Editor in Construct to edit the object's image. The plugin must have specified `SetHasImage(true)`.

GetAnimations()

Return an array of [IAnimation](#) representing the animations in the object type. Note this is only applicable to animated plugin types, e.g. Sprite.

AddAnimation(animName, frameBlob, frameWidth, frameHeight)

Add a new animation to the object type. The object type's plugin must be animated (e.g. the Sprite plugin). Animations must have at least one frame, so this method also adds an animation frame. The *frameBlob*, *frameWidth* and *frameHeight* parameters are all optional: if they are omitted, Construct will add a default empty animation frame. If they are provided they are interpreted the same way as [IAnimation.AddFrame\(\)](#); see the linked documentation for more details. The call returns a promise that resolves with the newly created [IAnimation](#).

GetAllInstances()

Return an array of all [IObjectInstances](#) or [IWorldInstances](#) of this object type in the project.

The returned instances may be placed on different layouts.

CreateWorldInstance(layer)

Create a new instance from this object type, and add it to the given [ILayer](#). Returns a new [IWorldInstance](#) interface representing the new instance. Note

this method is only applicable to `"world"` type plugins.

IsInContainer()

Return a boolean indicating if the object type belongs to a container.

GetContainer()

Return the [IContainer](#) the object type belongs to if any, else `null`.

CreateContainer(initialObjectTypes)

Create a new container using an array of [IObjectType](#) for the members of the container. The array must include the [IObjectType](#) this call is made on, must contain at least two elements, and the object type must not already be in a container. Returns an [IContainer](#) representing the created container.

IWORLDINSTANCE INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/object-interfaces/iworldinstance>

The `IWorldInstance` interface represents an instance of a "world" type plugin in Construct. It derives from [IObjectInstance](#).

Methods

GetLayer()

Return the [ILayer](#) this instance belongs to.

GetLayout()

Return the [ILayout](#) this instance belongs to.

GetBoundingBox()

Returns an [SDK.Rect](#) representing the bounding box of the instance in the layout.

GetQuad()

Returns an [SDK.Quad](#) representing the bounding quad of the instance in the layout.

GetColor()

Returns an [SDK.Color](#) representing the premultiplied color of the instance. This combines the instance's color tint with its opacity in the alpha channel.

SetOpacity(o)

GetOpacity()

Set or get the alpha component of the instance's color, representing its opacity, in the 0-1 range.

SetX(x)

SetY(y)

SetXY(x, y)

GetX()

GetY()

Set and get the position of this instance in layout co-ordinates.

SetZElevation(z)

GetZElevation()

Set and get the Z elevation (position on Z axis) of this instance. Note this is relative to the Z elevation of the layer the instance is on.

GetTotalZElevation()

Get the total Z elevation of this instance, which is its own Z elevation added to the Z elevation of the layer it is on.

SetAngle(a)

GetAngle()

Set and get the angle of the instance, in radians.

SetWidth(w)

SetHeight(h)

SetSize(w, h)

GetWidth()

GetHeight()

Set and get the size of the instance, in pixels.

SetOriginX(x)

SetOriginY(y)

SetOrigin(x, y)

GetOriginX()

GetOriginY()

Set and get the current origin of the instance in the layout. Note this is normalized to a [0, 1] range, e.g. 0.5 is the middle.

ApplyBlendMode(iRenderer)

Sets the current blend mode of the given [IWebGLRenderer](#) according to the *Blend mode* property of the instance in Construct. This is only relevant if the plugin specifies that it supports effects. Use this in the `Draw()` method to set the correct blend mode.

ILAYOUTVIEW INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/ui-interfaces/ilayoutview>

The `ILayoutView` interface provides access to a Layout View from the SDK. Note that this interface represents the editor view; the [ILayout](#) interface provides the interface to the actual layout in the project model.

Methods

GetProject()

Return the [IProject](#) representing the project associated with this Layout View.

GetLayout()

Return an [ILayout](#) representing the layout in the project model that this Layout View is showing.

GetActiveLayer()

Return an [ILayer](#) representing the current active layer selected in this Layout View.

GetZoomFactor()

Return the current zoom factor of the Layout View. For example 1 represents 100% zoom, 0.5 represents 50% zoom, etc.

LayoutToClientDeviceX(x)

LayoutToClientDeviceY(y)

Convert from layout co-ordinates to device pixel co-ordinates in the layout view canvas. This is useful for rendering at device pixel sizes after calling

```
SetDeviceTransform()
```

SetDeviceTransform(iRenderer)

Set the given [IWebGLRenderer](#) to a device pixel co-ordinate transform. This means co-ordinates used for rendering are based on device pixel co-ordinates relative to the layout view canvas, rather than layout co-ordinates.

SetDefaultTransform(iRenderer)

Set the given [IWebGLRenderer](#) to a layout co-ordinate transform. This is the default and should be restored after using `SetDeviceTransform()`.

Refresh()

Schedules the layout view to be redrawn at the next animation frame. Avoid unnecessarily refreshing the layout view, such as refreshing on a timer, since this can waste battery life.

UTIL INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/ui-interfaces/utilities>

The `SDK.UI.Util` interface provides access to various user interface utilities in the SDK.

Methods

AddDragDropFileHandler(callback, opts)

Register a callback for handling files drag-and-dropped in to the Construct 3 window. This is part of the Custom Importer API, allowing addons to handle importing files in a custom format. The given callback is invoked when a file is dropped in to the Construct 3 window, providing nothing else has handled it first. The callback must return a promise that resolves with `true` if the drop was recognised and imported, otherwise `false` if the drop was not recognised as a supported format (in which case Construct will continue running other handlers).

The `opts` parameter of `AddDragDropFileHandler()` is an options object, which may specify the following:

- `isZipFormat` : boolean indicating to handle dropped zip files only. If `true`, the callback will only be run if Construct recognises the dropped file as a zip file. Consequently the `file` parameter of the callback will be an [IZipFile](#), from which the contents of the zip file can be read. If `false`, the callback will only be run if Construct does *not* recognise the dropped file as a zip file, and consequently the `file` parameter of the callback will be a `Blob`.
- `toLayoutView` : boolean indicating to handle files dropped to an open Layout View only. If `true`, the callback will only be run if a Layout View is open, and the `opts` parameter of the callback will contain information about the Layout View and the drop position. If `false`, the callback will be run regardless of whether a Layout View is open or not, and no further options will be provided to the callback.

The `callback` should have the signature `async`

`function(filename, file, opts)`. The type of the `file` parameter is an `IZipFile` or `Blob` depending on the `isZipFormat` option. The `opts` parameter of the callback will provide the following additional details only when the `toLayoutView` option was specified:

- `layoutView`: an [ILayoutView](#) interface representing the Layout View that was open when the file was dropped. This also provides access to the associated project, layout, current active layer, and so on.
- `clientX` and `clientY`: the drop position within the window in client co-ordinates.
- `layoutX` and `layoutY`: the drop position within the Layout View in layout co-ordinates. This is the position to create any new instances relevant to.

static ShowLongTextPropertyDialog(text, caption)

Show the same dialog used to edit `longtext` properties. This is simply a large multi-line text field in a dialog, allowing for long text strings to be more conveniently edited, since the Properties Bar often can only show a small amount of text. Returns a promise that resolves with `null` if the dialog was cancelled, else a string of the text in the dialog.

FINDING ADDON IDS

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/finding-addon-ids>

Some APIs use special IDs, such as a plugin ID or action ID. The editor provides some methods you can use from the browser console to explore which IDs are available.

Listing addon IDs

The `C3SDK_ListAddonIDs (addonType)` method lists all installed addon IDs in the editor. The *addonType* parameter must be `"plugin"` or `"behavior"`. For example, load Construct 3 in a browser, open the browser console (usually F12), and enter the following call to list all plugin IDs:

```
C3SDK_ListAddonIDs("plugin")
```

This may take a moment to load, but then it will log to the console the ID for every installed plugin, along with its name as used in the editor (since this is sometimes different to the ID for legacy reasons).

Listing ACE IDs

The `C3SDK_ListACEIDs (addonType, addonId, aceType)` method lists the IDs for an addon's actions, conditions or expressions (ACEs). The parameters it takes are:

- *addonType*: as before, either `"plugin"` or `"behavior"`.
- *addonId*: the ID of the addon, which can be found using `C3SDK_ListAddonIDs()`.
- *aceType*: one of `"actions"`, `"conditions"` or `"expressions"`, determining which to list.

For example the following call will list all of the Sprite plugin's action IDs. The parameters each takes are also listed.

```
C3SDK_ListACEIDs("plugin", "Sprite", "actions")
```

IBEHAVIORINFO INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/ibehaviorinfo>

IBehaviorInfo defines the configuration for a behavior. It is typically accessed in the behavior constructor via `this._info`.

Methods

SetName(name)

Set the name of the addon. Typically this is read from the language file.

SetDescription(description)

Set the description of the addon. Typically this is read from the language file.

SetVersion(version)

Set the version string of the addon, in A.B.C.D form. Typically this is set to the `BEHAVIOR_VERSION` constant.

SetCategory(category)

Set the category of the addon. Typically this is set to the `BEHAVIOR_CATEGORY` constant. It must be one of `"attributes"`, `"general"`, `"movements"`, or `"other"`.

SetAuthor(author)

Set a string identifying the author of the addon.

SetHelpUrl(url)

Set a string specifying a URL where the user can view help and documentation resources for the addon.

SetIcon(url, type)

Set the addon icon URL and type. By default the URL is `"icon.svg"` and the type is `"image/svg+xml"`. It is recommended to leave this at the default and use an SVG icon, since it will scale well to any display size or density. However you can change your addon to load a PNG icon with `SetIcon("icon.png", "image/png")`.

SetIsOnlyOneAllowed(isOnlyOneAllowed)

Set a boolean of whether the behavior is allowed to be added more than once to the same object. The default is `false`, which means the behavior can be added multiple times to the same object. Set to `true` to only allow it to be added once to each object.

SetIsDeprecated(isDeprecated)

Set a boolean of whether the addon is deprecated or not. If you wish to replace your addon with another one, the old one can be deprecated with `SetIsDeprecated(true)`. This makes it invisible in the editor so it cannot be used in new projects; however old projects with the addon already added can continue to load and work as they did before. This discourages use of the deprecated addon without breaking existing projects that use it.

SetCanBeBundled(canBeBundled)

Pass `false` to prevent the addon from being bundled via the *Bundle addons* project property. By default all addons may be bundled with a project, and it is recommended to leave this enabled for best user convenience. However if you publish a commercial addon and want to prevent it being distributed by project-bundling, you may wish to disable this.

SetProperties(propertiesArray)

Set the available addon properties by passing an array of [PluginProperty](#). See [Configuring Behaviors](#) for more information.

AddCordovaPluginReference(opts)

Add a dependency on a Cordova plugin, that will be included when using the Cordova exporter. For more information see [Specifying dependencies](#).

AddFileDependency(opts)

Add a dependency on another file included in the addon. For more information see [Specifying dependencies](#).

AddRemoteScriptDependency(url) Not recommended

Add a script dependency to a remote URL (on a different origin). For more information see [Specifying dependencies](#).

IPLUGININFO INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/iplugininfo>

IPluginInfo defines the configuration for a plugin. It is typically accessed in the plugin constructor via `this._info`.

Methods

SetName(name)

Set the name of the addon. Typically this is read from the language file.

SetDescription(description)

Set the description of the addon. Typically this is read from the language file.

SetVersion(version)

Set the version string of the addon, in A.B.C.D form. Typically this is set to the `PLUGIN_VERSION` constant.

SetCategory(category)

Set the category of the addon. Typically this is set to the `PLUGIN_CATEGORY` constant. It must be one of `"data-and-storage"`, `"form-controls"`, `"general"`, `"input"`, `"media"`, `"monetisation"`, `"platform-specific"`, `"web"`, `"other"`.

SetAuthor(author)

Set a string identifying the author of the addon.

SetHelpUrl(url)

Set a string specifying a URL where the user can view help and documentation resources for the addon. The website should be hosted with HTTPS.

SetPluginType(type)

Set the plugin type. This can be `"object"` or `"world"`. The world type represents a plugin that appears in the Layout View, whereas the object type represents a hidden plugin, similar to the Audio plugin (a single-global type) or Dictionary. World type plugins must derive from `SDK.IWorldInstanceBase` instead of `SDK.IInstanceBase` and implement a `Draw()` method.

SetIcon(url, type)

Set the addon icon URL and type. By default the URL is `"icon.svg"` and the type is `"image/svg+xml"`. It is recommended to leave this at the default and use an SVG icon, since it will scale well to any display size or density. However you can change your addon to load a PNG icon with

```
setIcon("icon.png", "image/png")
```

SetIsResizable(isResizable)

For `"world"` type plugins only. Pass `true` to enable resizing instances in the Layout View.

SetIsRotatable(isRotatable)

For `"world"` type plugins only. Pass `true` to enable the *Angle* property and rotating instances in the Layout View.

SetIs3D(is3d)

For `"world"` type plugins only. Pass `true` to specify that this plugin renders in 3D. This will cause the presence of the plugin in a project to enable 3D rendering when the project *Rendering mode* property is set to *Auto* (which is the default setting).

SetHasImage(hasImage)

For `"world"` type plugins only. Pass `true` to add a single editable image, such as used by the Tiled Background plugin.

SetDefaultImageURL(url)

For plugins that use a single editable image only. Set the URL to an image file in your addon to use as the default image when the object is added to a project, e.g. `"default.png"`.

When using developer mode addons, remember to add the image file to the file list in `addon.json`.

SetIsTiled(isTiled)

For `"world"` type plugins only. Pass `true` to indicate that the image is intended to be tiled. This adjusts the texture wrapping mode when Construct creates a texture for its image.

SetIsDeprecated(isDeprecated)

Set a boolean of whether the addon is deprecated or not. If you wish to replace your addon with another one, the old one can be deprecated with

`SetIsDeprecated(true)` . This makes it invisible in the editor so it cannot be used in new projects; however old projects with the addon already added can continue to load and work as they did before. This discourages use of the deprecated addon without breaking existing projects that use it.

SetIsSingleGlobal(isSingleGlobal)

Pass `true` to set the plugin to be a *single-global* type. The plugin type must be `"object"` . Single-global plugins can only be added once to a project, and they then have a single permanent global instance available throughout the project. This is the mode that plugins like Touch and Audio use.

SetSupportsZElevation(supportsZElevation)

Pass `true` to allow using Z elevation with this plugin. The plugin type must be `"world"` . By default the renderer applies the Z elevation before calling the `Draw()` method on an instance, which in many cases is sufficient to handle rendering Z elevation correctly, but be sure to take in to account Z elevation in the drawing method if it does more complex rendering.

`AddCommonZOrderACEs()` will add common ACEs for Z elevation if supported.

SetSupportsColor(supportsColor)

Pass `true` to allow using the built-in color property to tint the object appearance. The plugin type must be `"world"` . By default the renderer sets the color before calling the `Draw()` method on an instance, which in many cases is sufficient to handle rendering with the applied color, but be sure to take in to account the instance color in the drawing method if it does more complex rendering.

`AddCommonAppearanceACEs()` will add common ACEs for color if supported.

SetSupportsEffects(supportsEffects)

Pass `true` to allow using effects, including the *Blend mode* property, with this plugin. The plugin type must be `"world"` . If the plugin does not simply draw a texture the size of the object (as Sprite does), you should also call

`SetMustPreDraw(true)` .

SetMustPreDraw(mustPreDraw)

Pass `true` to disable an optimisation in the effects engine for objects that simply draw a texture the size of the object (e.g. Sprite). This is necessary for

effects to render correctly if the plugin draws anything other than the equivalent the Sprite plugin would.

SetCanBeBundled(canBeBundled)

Pass `false` to prevent the addon from being bundled via the *Bundle addons* project property. By default all addons may be bundled with a project, and it is recommended to leave this enabled for best user convenience. However if you publish a commercial addon and want to prevent it being distributed by project-bundling, you may wish to disable this.

AddCommonPositionACEs()

AddCommonSceneGraphACEs()

AddCommonSizeACEs()

AddCommonAngleACEs()

AddCommonAppearanceACEs()

AddCommonZOrderACEs()

Add common built-in sets of actions, conditions and expressions (ACEs) to the plugin relating to various built-in features.

Note: if adding common scene graph ACes, your plugin must be prepared to handle being added in to a scene-graph hierarchy, and having its position, size and angle controlled automatically. It must also support all the properties modifiable by hierarchies, otherwise the scene graph feature may not work as expected.

SetProperties(propertiesArray)

Set the available addon properties by passing an array of [PluginProperty](#). See [Configuring Plugins](#) for more information.

AddCordovaPluginReference(opts)

Add a dependency on a Cordova plugin, that will be included when using the Cordova exporter. For more information see [Specifying dependencies](#).

AddFileDependency(opts)

Add a dependency on another file included in the addon. For more information see [Specifying dependencies](#).

AddRemoteScriptDependency(url) Not recommended

Add a script dependency to a remote URL (on a different origin). For more information see [Specifying dependencies](#).

SetGooglePlayServicesEnabled(enabled)

Pass `true` to enable Google Play Services in Cordova Android exports.

```
<preference name="GradlePluginGoogleServicesEnabled" value="true" />
```

 will be added in config.xml.

Since this can only be configured once, if any plugin in the project specifies to enable Google Play Services, it will be enabled for the entire project.

SetDOMSideScripts(arr)

Specify an array of script paths to load in the main document context rather than the runtime context. For more information see the section *DOM calls in the C3 runtime* in [Runtime scripts](#).

PLUGINPROPERTY CLASS

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/pluginproperty>

PluginProperty defines a single property for an addon that will appear in the Properties Bar. Typically an array of PluginProperty is passed to `this._info.SetProperties()`. See [Configuring Plugins](#) for more information. Note that despite the name, PluginProperty is also used to define properties for behaviors.

Note properties do not directly define any strings that appear in the editor UI. These are defined in [The Language File](#).

Constructor

```
new SDK.PluginProperty(type, id, initialValue_or_options)
```

type

The type of the property. This can be one of:

- `"integer"` â€” an integer number property, always rounded to a whole number.
- `"float"` â€” a floating-point number property.
- `"percent"` â€” a floating-point number in the range [0-1] represented as a percentage. For example if the user enters 50%, the property will be set to a value of 0.5.
- `"text"` â€” a field the user can enter a string in to.
- `"longtext"` â€” the same as `"text"`, but a button with an ellipsis ("...") appears on the right side of the field. The user can click this button to open a dialog to edit a long string more conveniently. This is useful for potentially long content like the project description, or the main text of the Text object.

- `"check"` â€” a checkbox property, returning a boolean.
- `"font"` â€” a field which displays the name of a font and provides a button to open a font picker dialog. The property is set to a string of the name of the font.
- `"combo"` â€” a dropdown list property. The property is set to the zero-based index of the chosen item. The `items` field of the options object must be used to specify the available items.
- `"color"` For plugins only â€” a color picker property. The initial value must be an array, e.g. `[1, 0, 0]` for red.
- `"object"` For plugins only â€” an object picker property allowing the user to pick an object class. Note: At runtime, this passes a SID (Serialization ID) for the chosen object class, or -1 if none was picked. Use the runtime method [GetObjectClassBySID](#) to look up the corresponding ObjectClass.
- `"group"` â€” creates a new group in the Properties Bar. There is no value associated with this property.
- `"link"` For plugins only â€” creates a clickable link in the Properties Bar. There is no value associated with this property. A `linkCallback` function must be specified in the options object.
- `"info"` â€” creates a read-only string that cannot be edited. There is no value associated with this property. A `infoCallback` function must be specified in the options object.

id

A string of the ID for the property. This is used in the language file to identify related strings.

initialValue_or_options

For many properties, the only extra information needed is the initial value. For example for a `"float"` parameter this parameter can be a number of the

initial value to use for the property. However to configure more options for the property, pass an object instead, and see the section on using an options object below. Some property types require the use of an options object, e.g.

`"combo"` requires it to specify the item list.

The options object

If the third parameter of the constructor is an object, use the following properties to specify further configuration of the property.

initialValue

Specify the initial value for the property, since the third parameter is occupied by the options object. Note when using a `"combo"` type this must be a string of the initial item ID, and when using a `"color"` type, this must be a normalized RGB array, e.g. `[1, 0, 0]` for red.

minValue

Specify a minimum value for a numeric property.

maxValue

Specify a maximum value for a numeric property.

items

Only valid with the `"combo"` property type. Specify an array of strings representing the available item IDs in the dropdown list. The actual displayed strings are read from the language file.

dragSpeedMultiplier

Only valid with numeric properties. Pass a ratio to modify how quickly the value changes when it is being dragged up or down. For example passing 2 would cause the value to increase twice as fast as the mouse moves while dragging the value.

allowedPluginIds

For `"object"` type properties only. An array of plugin ID strings to filter the object picker by. This can also contain the special string `"<world>"` to allow any world-type plugin.

linkCallback

For `"link"` type properties only. A function that is called when the link is clicked. The number of calls, and the type of the parameter, are determined by the `callbackType` option.

callbackType

For `"link"` type properties only. Specifies how the link callback function is used. This can be one of the following:

- `"for-each-instance"` default – the callback is run once per selected instance in the Layout View. The callback parameter is an [IWorldInstance](#). This is useful for per-instance modifications, such as a link to make all instances their original size.
- `"once-for-type"` – the callback is run once regardless of how many instances are selected in the Layout View. The callback parameter is an [IObjectType](#). This is useful for per-type modifications, such as a link to edit the object image.

infoCallback

For `"info"` type properties only. A function that is called to get the value to display as a read-only string. The function is automatically called when any other properties change. The parameter is an instance of your addon, which you can use to read other property values and use them in the returned value.

interpolatable

For `"integer"`, `"float"`, `"percent"`, `"text"`, `"longtext"`, `"check"`, `"combo"` and `"color"` type properties only. Has a default value of `false`, set to `true` so the property can be supported by timelines. In order to fully support timelines it is also needed to follow the [Timeline Integration Guide](#).

SPECIFYING DEPENDENCIES

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/reference/specifying-dependencies>

Plugins and behaviors can specify dependencies on additional files, or Cordova plugins for inclusion with the Cordova exporter. Dependencies are added using the `AddFileDependency(opts)` and

`AddCordovaPluginReference(opts)` methods on both [IPluginInfo](#) and [IBehaviorInfo](#). Remote scripts can also be added with

`AddRemoteScriptDependency`, but this is not recommended.

File dependencies

A file dependency refers to another file in the addon. Note the file must be bundled with the addon; you cannot refer to URLs elsewhere on the Internet.

There are five kinds of file dependency, which correspond to the `type` property in the options object:

copy-to-output

This simply causes the file to be copied to the output folder when exporting. The file is also available in preview mode. This is useful for bundling additional resources, such as an image file that needs to be loaded at runtime, or a script that is dynamically loaded.

inline-script

A script dependency that is directly included in the output script file (normally named `c3runtime.js`).

Consequently this script will also be minified on export along with the addon runtime script. This is a convenient way to break up a large runtime script.

external-dom-script

A script dependency that is included via the addition of an extra `<script>` tag in the exported HTML file. Note in worker mode the script is loaded in the DOM, so is not directly available to the runtime code in the worker. The script is not minified on export. This is suitable for large external libraries that the addon references.

For backwards-compatibility reasons, the type `external-script` is treated as `external-dom-script`.

external-runtime-script

A script dependency that is included via the addition of an extra `<script>` tag in the exported HTML file, or loaded on the worker with `importScripts()` in worker mode. This means the script is always directly available to runtime code. However the dependency must be designed to work in a Web Worker, e.g. not assuming the DOM is present. The script is not minified on export.

external-css

A stylesheet dependency that is included via the addition of an extra `<link rel="stylesheet">` tag in the exported HTML file, in case the addon needs to specify CSS styles.

To add a file dependency, call `AddFileDependency` with an options object, such as in this example:

```
this._info.AddFileDependency({
  filename: "mydependency.js",
  type: "external-script"
});
```

The options object uses the following properties.

filename

Name of the dependency file in the addon. This must be bundled with the addon; it cannot refer to a URL. It is recommended to bundle the script with your addon, but if you must use a URL, see the section *Remote script dependencies*. The file path is relative to the root (the location of `addon.json`).

For developer mode addons, make sure the dependency file is also included in the `"file-list"` key. For more information see the section on Developer mode addons in [Addon metadata](#).

type

One of the types described above, e.g. `"external-script"`.

fileType

When `type` is `"copy-to-output"`, this must specify the MIME type of the file. For example if including `"image.png"` as a `"copy-to-output"` dependency, the `fileType`

must be set to `"image/png"` .

Cordova plugin dependencies

Addons can specify dependencies on Cordova plugins. These only apply to the Cordova exporter, which covers both Android and iOS. When exporting a Cordova project, the additional Cordova plugin dependencies are automatically included in the exported config.xml. This allows convenient integration of a Construct addon with a Cordova plugin.

To add a Cordova plugin dependency, call `AddCordovaPluginReference` with an options object, such as in this example:

```
this._info.AddCordovaPluginReference({
  id: "cordova-plugin-inappbrowser"
});
```

If you wish to provide variables to the Cordova plugin, use the `variables` property of the options object to pass an array of `[variableName, pluginProperty]` pairs. In this case the plugin must also be passed in the `plugin` property. An example is shown below.

```
const property = new SDK.PluginProperty("integer", "test-property",
  0);

this._info.SetProperties([
  property
]);

this._info.AddCordovaPluginReference({
  id: "cordova-plugin-inappbrowser",
  plugin: this,
  variables: [
    ["MY_VAR", property]
  ]
});
```

Cordova plugins that require variables will not compile if the variable is omitted from config.xml.

See [Cordova plugin variables](#) for more information.

The options object uses the following properties.

id

The ID of the Cordova plugin to reference.

version Optional

A version spec for the Cordova plugin, e.g. `"1.0.4"`. If this is not specified, the latest version will be used.

platform Optional

Specify a specific platform the Cordova plugin applies to. By default this is `"all"` meaning it will be used in both Android and iOS exports. However it can be set to `"android"` or `"ios"` to only be included when exporting to a specific platform. This is useful to switch between different Cordova plugins on different platforms.

variables Optional

Specify variables to be used with the Cordova plugin as an array of `[variableName, pluginProperty]` pairs. The variable name is bound to a `SDK.PluginProperty`. When the project is exported a variable is added under the plugin reference in `config.xml` with the given name and a value taken from the specified property. When variables are specified, the `plugin` property must also be set.

plugin Optional

Used to specify the plugin when using variables. Normally this should be set to `this`.

Note for security reasons the Scirra mobile app build service does not allow arbitrary Cordova plugins to be used. The build service uses an allowlist of allowed Cordova plugins. If you'd like a Cordova plugin to be added to the allowlist, please file an issue on the [Construct 3 issue tracker](#). Please note we cannot guarantee that Cordova plugins will be allowed, and approval is subject to a security review. Other build services, such as using PhoneGap Build or compiling with the Cordova CLI, do not impose this restriction.

Remote script dependencies

Plugins and behaviors may also specify remote script dependencies. These are loaded from a cross-origin URL, e.g. `https://example.com/api.js`.

Avoid using remote script dependencies where possible. They have some drawbacks:

- *Construct 3 games work offline. However remote scripts cannot be cached for offline use, so will fail to load when the user is offline.*
- *Remote scripts can also fail to load due to unreliable connections or service outages.*
- *In some native apps, e.g. Cordova on Android/iOS, the native platform may block any access to URLs that are not on an allowlist of allowed origins. This can cause the script to fail to load unless the user does additional configuration of their app.*

Prefer using a file dependency instead, and bundle the script with your addon. If you must use a remote script, ensure your addon gracefully handles the case the remote script fails to load.

Use `AddRemoteScriptDependency` to add a remote URL to load a script from, e.g.:

```
this._info.AddRemoteScriptDependency("https://example.com/api.js");
```

This will produce the following tag on export, loaded before the runtime:

```
<script src="https://example.com/api.js"></script>
```

The script URL must not use `http:` in its URL. On the modern web this will often be blocked from secure sites as mixed content. You must either use secure HTTPS, or a same-protocol URL like

```
//example.com/api.js.
```

ARRAY APIS

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/addon-interfaces/array>

The built-in Array plugin SDK instance exposes the following APIs.

At(x, y, z)

Retrieve an element from the array at the given X, Y and Z co-ordinates. For one or two dimensional access, pass 0 for the unused components.

Set(x, y, z, val)

Set an element in the array at the given X, Y and Z co-ordinates. For one or two dimensional access, pass 0 for the unused components.

Only store number or string primitives in the array, or the plugin will cease to work correctly.

SetSize(w, h, d)

Set the size of the array in up to three dimensions. For one or two dimensional arrays, pass 1 for the unused dimensions. (Note passing 0 for any dimension will create an array with zero elements that cannot store any data.) If the array grows, new elements have the value 0. If the array shrinks, elements are removed.

GetWidth()

GetHeight()

GetDepth()

Retrieve the current dimensions of the array.

BINARY DATA APIS

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/addon-interfaces/binary-data>

The built-in Array plugin SDK instance exposes the following APIs.

You can filter object parameters by the Binary Data's plugin ID `"BinaryData"` to ensure the user can only pick Binary Data objects for any conditions or actions that integrate with it.

SetArrayBufferCopy(viewOrBuffer)

Set the contents of the Binary Data object by copying `viewOrBuffer`, which can be either an ArrayBuffer or a typed array.

SetArrayBufferTransfer(arrayBuffer)

Set the contents of the Binary Object by taking ownership of the passed ArrayBuffer. This avoids copying the data, but the caller must not use the passed ArrayBuffer any more.

GetArrayBufferCopy()

Return an ArrayBuffer which is a copy of the contents of the Binary Data object. Since a copy is returned the caller may modify the returned ArrayBuffer.

GetArrayBufferReadOnly()

Return a direct reference to the ArrayBuffer representing the contents of the Binary Data object. This must not be modified by the caller. However this avoids copying the data if used for read-only purposes, e.g. sending down a WebSocket.

DICTIONARY APIS

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/addon-interfaces/dictionary>

The built-in Dictionary plugin SDK instance exposes the following APIs.

GetDataMap()

Return the [Map](#) which is used as the underlying data storage for the Dictionary object. This allows access to add, change, remove and iterate items.

Only use string keys, and only store number or string primitives as key values, or the plugin will cease to work correctly.

DRAWING CANVAS APIS

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/addon-interfaces/drawing-canvas>

The built-in Drawing canvas plugin exposes the following APIs.

Drawing canvas instance APIs

async GetImagePixelData()

Takes a snapshot of the drawing canvas pixel state on the GPU, and reads it back to the CPU asynchronously. Resolves with an [ImageData](#) representing the pixel data. Note this uses unpremultiplied alpha, whereas the surface on the GPU is premultiplied, so technically this is lossy.

FACEBOOK APIS

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/addon-interfaces/facebook>

The built-in Facebook plugin SDK instance exposes the following APIs.

Getting the Facebook instance

When a project uses the Facebook plugin, the `ObjectClass` for it can be looked up using the runtime method

`GetSingleGlobalObjectClassByCtor(C3.Plugins.Facebook)`. From there the single-global instance can be obtained and then the SDK instance, which exposes the API below. Note that if the Facebook plugin is not present in the project then `GetSingleGlobalObjectClassByCtor()` will return `null`. The code sample below demonstrates how to access the Facebook plugin instance from another addon.

```
const facebookObjectClass = this._runtime.GetSingleGlobalObjectClassByCtor(C3.Plugins.Facebook);
if (facebookObjectClass)
{
    const facebookSdkInst = facebookObjectClass.GetSingleGlobalInstance().GetSdkInstance();
    // can now make calls, e.g.: facebookSdkInst.GetAccessToken()
}
```

Available APIs

GetAccessToken()

Return a string of the Facebook login access token. This is available once the *On user logged in* trigger fires. The access token can be used to make additional Facebook API calls on behalf of the user.

FUNCTION APIS

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/addon-interfaces/function>

When the Function plugin is present in a project, it creates a global function that can be used to invoke a function from JavaScript. Note this function does not exist if the Function plugin is not present in the project, so calling code should check for the existence of the method first. An example is included below.

```
if (self.c2_callFunction)
    self.c2_callFunction("name", ["param1", "param2"]);
```

self.c2_callFunction(name, params)

In the C3 runtime, the name `c3_callFunction` can also be used.

Synchronously trigger the function with the given *name* in the event system. *params* is optional and can be omitted if no parameters are to be passed; otherwise it must be an array of the parameters to pass. Parameters may only be string or number primitives - any other types will return as 0 in Construct. If the function in the event system returns a value, it is also returned by this method, and also can only return a string or number primitive.

Do not use this method with the scripting feature in Construct. It is intended only for the Addon SDK. When writing JavaScript code in the Construct editor, use [runtime.callFunction\(\)](#) instead.

TILEMAP APIS

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/addon-interfaces/tilemap>

The built-in Tilemap plugin exposes the following APIs allowing manipulation of the tiles in the tilemap.

Tile numbers

Tiles in the tilemap are represented as a single 32-bit integer number and can be rotated and flipped. To support this they consist of two parts using a bitmask:

- The tile ID in the lower 29 bits - this is the number of the tile as shown in the Tilemap Bar when hovering the tile
- Tile flags in the upper 3 bits

There is also a special tile number -1 indicating an empty tile.

Tile flags

The Tilemap plugin exposes the following flags and masks which can be used to manipulate tile numbers:

```
C3.Plugins.Tilemap.TILE_FLIPPED_HORIZONTAL = -0x80000000;  
C3.Plugins.Tilemap.TILE_FLIPPED_VERTICAL = 0x40000000;  
C3.Plugins.Tilemap.TILE_FLIPPED_DIAGONAL = 0x20000000;  
C3.Plugins.Tilemap.TILE_FLAGS_MASK = 0xE0000000;  
C3.Plugins.Tilemap.TILE_ID_MASK = 0x1FFFFFFF;
```

For example, to flip tile ID 2 horizontally, you would use bitwise OR combining the tile ID and the flag, e.g. `2 |`

`C3.Plugins.Tilemap.TILE_FLIPPED_HORIZONTAL`. Similarly you can test if the bit is set using `tile &`

`C3.Plugins.Tilemap.TILE_FLIPPED_HORIZONTAL`.

You can also use the masks to extract each component of the tile number. For example `tile & C3.Plugins.Tilemap.TILE_ID_MASK` will return just the tile ID, since it removes all the flag bits.

Be sure to first check if the tile is the special value -1 indicating an empty tile. This is a special value that doesn't use the bit representation so won't

work when combined with flags or masks.

Tilemap instance APIs

GetTileWidth()

GetTileHeight()

Get the size of a tile in pixels.

GetMapWidth()

GetMapHeight()

Get the size of the tilemap in tiles.

GetTileAt(x, y)

Get the tile at a given position in tiles (i.e. (0, 0) is the top-left tile of the tilemap, regardless of the tilemap's position or the tile size). Returns -1 for empty tiles or tiles outside the tilemap; otherwise use bit operations to determine tile ID or flags separately.

SetTileAt(x, y, tile)

Set the tile at a given position in tiles. Use -1 to set a tile empty; otherwise use bit operations to combine the tile ID and flags.

DOMELEMENTHANDLER INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/base-classes/domelementhandler>

The `DOMElementHandler` interface is used as a base class for DOM handlers in the DOM-side script (typically `domSide.js`). See [DOM calls in the C3 runtime](#) for more information.

Note that all other base classes are created on the runtime side - i.e. in a Web Worker when in worker mode. This base class is always created on the DOM side - i.e. where the `document` object can be accessed.

Methods

AddDOMElementMessageHandler(handler, func)

Add a message handler to receive messages sent by

`PostToDOMElement()` / `PostToDOMElementAsync()` in [SDKDOMInstanceBase](#). The `handler` should match the string the message was posted with. `func` receives the arguments `(elem, e)`, providing both the associated DOM element and the `data` argument the message was posted with, if any. When the `PostToDOMElementAsync()` variant is used, `func` can be an async method, and it will be awaited and its return value sent back to the runtime to resolve the returned promise.

PostToRuntimeElement(handler, elementId, data)

Post a message to the runtime about this element. For example you could post a `"click"` message when the element is clicked, in order to trigger *On clicked* in the runtime. The message is received by

`AddElementMessageHandler()` in [SDKDOMPluginBase](#). `handler` is a string identifying the message. `elementId` identifies the element and is used to find the associated runtime instance; pass the element ID provided in `CreateElement()`. `data` is an optional extra JSON object to pass along to the message handler.

CreateElement(elementId, e)

Override to create your plugin's DOM element. Note since an element has not been created yet, the runtime identifies it by an assigned `elementId`, which

needs to be passed along to some other calls. The element state is also passed as an argument.

DestroyElement(elem)

Optional override called when the runtime destroys the instance associated with this DOM element. The runtime automatically removes the element from the DOM, but this provides an opportunity for additional cleanup.

UpdateState(elem, e)

Override to update the state of the DOM element according to the element state retrieved from `GetElementState()` in [SDKDOMInstanceBase](#).

DOMHANDLER INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/base-classes/domhandler>

The `DOMHandler` interface is a base class for DOM-side scripts (typically in `domSide.js`). This means it does not have access to the runtime, since in Web Worker mode the runtime is hosted in a separate JavaScript context within the worker. However the DOM-side script does have access to the full DOM APIs, e.g. `document`, and using the messaging methods can communicate with the runtime. See [DOM calls in the C3 runtime](#) for more information.

Methods

AddRuntimeMessageHandler(handler, callback)

AddRuntimeMessageHandlers(arr)

Add a callback to be run to handle a message posted from a runtime-side script. The handler is a string identifier. The callback receives the posted data as an argument. Note that if the caller in the runtime-side script originally used the `PostToDOMAsync` method, the callback may be an `async` function, and the return value is posted back to the runtime-side script. The `AddRuntimeMessageHandlers` variant accepts an array of `[handler, callback]` which is convenient when adding multiple handlers.

PostToRuntime(handler, data)

PostToRuntimeAsync(handler, data)

Post a message to a runtime-side script. The handler is a string identifier. The `data` must be [structurally clonable](#) (since it is posted down a `MessageChannel`). The `async` method returns a promise that resolves with the runtime-side callback's return value. The non-`async` method does not return a value and the runtime-side callback's return value is discarded (i.e. a "fire and forget" message).

SDKBEHAVIORBASE INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/base-classes/sdkbehaviorbase>

The `SDKBehaviorBase` interface is used as the base class for your behavior in the runtime. It is the behavior equivalent of [SDKPluginBase](#).

`SDKBehaviorBase` cannot be directly constructed; it should only be used as a base class.

Properties

`this._runtime`

Reference to the associated [Runtime](#) that controls execution of the project.

Methods

`GetRuntime()`

Returns `this._runtime` publicly.

`OnCreate()`

Optional override called by the runtime when the behavior is created. This is done early on in the loading process.

`GetObjectClasses()`

Return a read-only array of [ObjectClass](#) that use this kind of behavior. The order is undefined.

`GetInstances()`

Return a read-only array of [Instance](#) that use this kind of behavior. The order is undefined.

SDKBEHAVIORINSTANCE INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/base-classes/sdkbehaviorinstancebase>

The `SDKBehaviorInstance` interface is used as the base class for runtime behavior instances in the SDK. When a behavior is added to an object type, each of its object instances has a behavior instance created and associated with it.

`SDKBehaviorInstance` cannot be directly constructed; it should only be used as a base class.

Properties

this._behInst

Reference to the [BehaviorInstance](#) representing this behavior instance in the runtime. This allows access to Construct's built-in runtime features for behavior instances.

this._inst

Reference to the [Instance](#) representing the associated instance in the runtime. This is the object instance that the behavior can control.

this._runtime

Reference to the associated [Runtime](#) that controls execution of the project.

this._behaviorType

Reference to the [BehaviorType](#) representing the behavior type that this instance belongs to.

this._sdkType

Reference to your addon's SDK behavior type class, which derives from [SDKBehaviorTypeBase](#).

Methods

Release()

Optional override for when a behavior instance is released.

GetBehaviorInstance()

Returns `this._behInst` publicly.

GetObjectInstance()

Returns `this._inst` publicly.

GetWorldInfo()

Returns `this._inst.GetWorldInfo()`, i.e. the [WorldInfo](#) for the associated object instance. Note this is only applicable when added to "world" type plugins, otherwise it returns `null`.

GetRuntime()

Returns `this._runtime` publicly.

GetObjectClass()

Returns `this._objectClass` publicly.

GetBehaviorType()

Returns `this._behaviorType` publicly.

GetSdkType()

Returns `this._sdkType` publicly.

GetBehavior()

Returns your addon's SDK behavior class, which derives from [SDKBehaviorBase](#).

PostCreate()

Optional override called after the associated object instance has finished being created. This is useful since the behavior instance constructor is called during instance creation, so the final state is not ready yet.

Trigger(method)

Fire a trigger condition. The condition must be declared as a trigger in `aces.json`. Pass a full reference to the condition method, e.g.

```
this.Trigger(C3.Behaviors.Bullet.Cnds.OnStep).
```

_StartTicking()

_StartTicking2()

_StartPostTicking()

IsTicking()

IsTicking2()

IsPostTicking()

_StopTicking()

_StopTicking2()

_StopPostTicking()

Utility methods to start or stop the runtime calling the `Tick()`, `Tick2()` or `PostTick()` methods of your instance every tick, and also to check whether ticking is active. It is recommended to stop ticking whenever the tick method is no longer needed to reduce the performance overhead of ticking. Redundant calls to start or stop ticking are ignored. The first call always takes effect (i.e. calls do not stack - if you make 3 calls to start ticking then 1 call to stop ticking, ticking is stopped).

Tick()

Optional override that is called every tick just before events are run after `_StartTicking()` has been called.

Tick2()

Optional override that is called every tick just after events are run after `_StartTicking2()` has been called.

PostTick()

Optional override that is called every tick just after all other behaviors have had their `Tick()` methods called. This allows behaviors to observe the state applied by other behavior's ticking. Note you should use `Tick()` rather than `PostTick()` where possible, since it is not possible to reliably observe the state applied by other behavior's post-ticking.

GetDebuggerProperties()

Override to return properties to display in the debugger. For more information see [runtime scripts](#).

SaveToJson()

Optional override to return a JSON object that represents the state of the instance for savegames.

LoadFromJson(o)

Optional override accepting a JSON object returned by a prior call to `SaveToJson()` that represents the state of an instance to load, for savegames.

CallAction(actMethod, ...args)

Avoid using this wherever possible. It usually indicates poor design. Actions are intended to be used in event sheets only and are not meant to act like an API. Use normal JavaScript method calls instead.

Convenience method to run an action method with the given parameters. For example:

```
this.CallAction(C3.Behaviors.MyAddon.Acts.MyAction,  
"foo", "bar")
```

CallExpression(expMethod, ...args)

Avoid using this wherever possible. It usually indicates poor design. Expressions are intended to be used in event sheets only and are not meant to act like an API. Use normal JavaScript method calls instead.

Convenience method to run an expression method with the given parameters. Returns the value returned by the expression. For example:

```
const value  
=  
this.CallExpression(C3.Behaviors.MyAddon.Exps.MyExpression)
```

GetScriptInterfaceClass()

Return a custom class to instantiate for the script interface in Construct's scripting feature. See the [SDK downloads](#) for sample usage of a custom script interface.

GetScriptInterface()

Return the actual script interface used for this behavior instance in Construct's scripting feature. This is an [BehaviorInstance](#) or derivative.

DispatchScriptEvent(name, cancelable, additionalProperties)

Fire an event on the script interface for the behavior instance (as with `dispatchEvent()` on the script interface). `name` is a string of the event name. `cancelable` is a boolean indicating if the event can be stopped with `preventDefault()`. The event object will have the default properties as described in [Behavior instance event](#) in the scripting reference. Additional properties can optionally be set by passing an object for `additionalProperties` whose properties will be added to the event object. For example: `DispatchScriptEvent("myevent", false, { extraProperty: 5 })`

SDKBEHAVIORTYPEBASE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/base-classes/sdkbehaviortypebase>

The `SDKBehaviorTypeBase` interface is used as the base class for runtime behavior types in the SDK. A behavior type corresponds to a behavior listed in the Behaviors dialog. Behavior types have multiple behavior instances, each associated with an object instance. It is the behavior equivalent of [SDKTypeBase](#).

`SDKBehaviorTypeBase` cannot be directly constructed; it should only be used as a base class.

Properties

this._objectClass

Reference to the [ObjectClass](#) representing the object type that this behavior type belongs to.

this._behaviorType

Reference to the [BehaviorType](#) representing this behavior type in the runtime.

this._runtime

Reference to the associated [Runtime](#) that controls execution of the project.

this._behavior

Reference to your addon's SDK behavior class, which derives from [SDKBehaviorBase](#).

Methods

GetObjectClass()

Returns `this._objectClass` publicly.

GetBehaviorType()

Returns `this._behaviorType` publicly.

GetRuntime()

Returns `this._runtime` publicly.

GetBehavior()

Returns `this._behavior` publicly.

SDKDOMINSTANCEBASE INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/base-classes/sdkdominstancebase>

The `SDKDOMInstanceBase` interface is used as the base class for runtime instances that create a DOM element. It derives from [SDKWorldInstanceBase](#).

`SDKDOMInstanceBase` cannot be directly constructed; it should only be used as a base class.

Methods

PostToDOMElement(handler, data)

PostToDOMElementAsync(handler, data)

Post a message from the runtime instance to the DOM side. The message is received using `AddDOMElementMessageHandler()` in [DOMElementHandler](#). `handler` is a string identifying the kind of message. `data` is a JSON object that is forwarded with the message to provide additional details. The async variant returns a promise that awaits an async handler on the DOM side and forwards the return value back to the runtime, which the returned promise resolves with. The non-async variant simply posts a message and ignores the result (i.e. fire-and-forget).

CreateElement(data)

Instruct the runtime to create a DOM element for this instance. It will end up calling `CreateElement()` in [DOMElementHandler](#) with `data` (an optional object with additional details to create with). The runtime associates the resulting element with this instance.

FocusElement()

BlurElement()

Helper methods to manage calling `focus()` and `blur()` on the instance's associated DOM element.

SetElementCSSStyle(prop, val)

Helper method to set a CSS style on the instance's associated DOM element. For example `SetElementCSSStyle("font-family", "sans-serif")` will be forwarded to `elem.style.fontFamily = "sans-`

`serif"` on the DOM side.

GetElementState()

Override to return a JSON object representing the state of the DOM element, e.g. the text content. This is used by `CreateElement()` and `UpdateElementState()` to retrieve state to pass to the DOM side.

UpdateElementState()

Send a message from the runtime to the DOM side with the element state (retrieved from `GetElementState()`). This results in a call to `UpdateState(elem, e)` on the DOM side. This is a convenient way to make sure any changes to the DOM element are applied.

SDKDOMPLUGINBASE INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/base-classes/sdkdompluginbase>

The `SDKDOMPluginBase` interface is used as the base class for a plugin in the runtime that manages a DOM element. Note the constructor also requires passing the `DOM_COMPONENT_ID`. See the section [DOM calls in the C3 runtime](#) for more information.

`SDKDOMPluginBase` cannot be directly constructed; it should only be used as a base class.

`SDKDOMPluginBase` derives from [SDKPluginBase](#).

Methods

AddElementMessageHandler(handler, func)

Add a message handler to receive messages posted by

`PostToRuntimeElement()` in [DOMElementHandler](#). `handler` must match the string passed to `PostToRuntimeElement()`. `func` accepts two arguments: the SDK instance, and an optional object with extra details passed to `PostToRuntimeElement()`. Typically this function simply forwards the handler to an instance method, e.g.

```
this.AddElementMessageHandler("click", (sdkInst, e) =>
sdkInst._OnClick(e));
```

SDKINSTANCEBASE INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/base-classes/sdkinstancebase>

The `SDKInstanceBase` interface is used as the base class for runtime instances in the SDK. For "world" type plugins, instances instead derive from [SDKWorldInstanceBase](#) which itself derives from `SDKInstanceBase`.

`SDKInstanceBase` cannot be directly constructed; it should only be used as a base class.

Properties

`this._inst`

Reference to the [Instance](#) representing this instance in the runtime. This allows access to Construct's built-in runtime features for instances.

`this._runtime`

Reference to the associated [Runtime](#) that controls execution of the project.

`this._objectClass`

Reference to the [ObjectClass](#) representing the object type that this instance belongs to.

`this._sdkType`

Reference to your addon's SDK type class, which derives from [SDKTypeBase](#).

Methods

`Release()`

Optional override for when an instance is released.

`GetInstance()`

Returns `this._inst` publicly.

`GetRuntime()`

Returns `this._runtime` publicly.

GetObjectClass()

Returns `this._objectClass` publicly.

GetSdkType()

Returns `this._sdkType` publicly.

GetPlugin()

Returns your addon's SDK plugin class, which derives from [SDKPluginBase](#).

Trigger(method)

Fire a trigger condition. The condition must be declared as a trigger in `aces.json`. Pass a full reference to the condition method, e.g.

```
this.Trigger(C3.Plugins.Sprite.Cnds.OnAnimFinished) .
```

AddDOMMessageHandler(handler, callback)

AddDOMMessageHandlers(arr)

Add a callback to be run to handle a message posted from a DOM-side script. The handler is a string identifier. The callback receives the posted data as an argument. Note that if the caller in the DOM-side script originally used the `PostToRuntimeAsync` method, the callback may be an `async` function, and the return value is posted back to the DOM-side script. The

`AddDOMMessageHandlers` variant accepts an array of `[handler, callback]` which is convenient when adding multiple handlers.

PostToDOM(handler, data)

PostToDOMAsync(handler, data)

Post a message to a DOM-side script. The handler is a string identifier. The `data` must be [structurally clonable](#) (since it is posted down a `MessageChannel`).

The `async` method returns a promise that resolves with the DOM-side callback's return value. The non-`async` method does not return a value and the DOM-side callback's return value is discarded (i.e. a "fire and forget" message).

_StartTicking()

_StartTicking2()

IsTicking()

IsTicking2()

_StopTicking()

_StopTicking2()

Utility methods to start or stop the runtime calling the `Tick()` or `Tick2()` methods of your instance every tick, and also to check whether ticking is active. It is recommended to stop ticking whenever the tick method is no longer needed

to reduce the performance overhead of ticking. Redundant calls to start or stop ticking are ignored. The first call always takes effect (i.e. calls do not stack - if you make 3 calls to start ticking then 1 call to stop ticking, ticking is stopped).

Tick()

Optional override that is called every tick just before events are run after `_StartTicking()` has been called.

Tick2()

Optional override that is called every tick just after events are run after `_StartTicking2()` has been called.

GetDebuggerProperties()

Override to return properties to display in the debugger. For more information see [runtime scripts](#).

SaveToJson()

Optional override to return a JSON object that represents the state of the instance for savegames.

LoadFromJson(o)

Optional override accepting a JSON object returned by a prior call to `SaveToJson()` that represents the state of an instance to load, for savegames.

CallAction(actMethod, ...args)

Avoid using this wherever possible. It usually indicates poor design. Actions are intended to be used in event sheets only and are not meant to act like an API. Use normal JavaScript method calls instead.

Convenience method to run an action method with the given parameters. For example: `this.CallAction(C3.Plugins.MyAddon.Acts.MyAction, "foo", "bar")`

CallExpression(expMethod, ...args)

Avoid using this wherever possible. It usually indicates poor design. Expressions are intended to be used in event sheets only and are not meant to act like an API. Use normal JavaScript method calls instead.

Convenience method to run an expression method with the given parameters. Returns the value returned by the expression. For example: `const value`

```
this.CallExpression(C3.Plugins.MyAddon.Exps.MyExpression)
```

GetScriptInterfaceClass()

Return a custom class to instantiate for the script interface in Construct's scripting feature. See the [SDK downloads](#) for sample usage of a custom script interface.

GetScriptInterface()

Return the actual script interface used for this instance in Construct's scripting feature. This is an [Instance](#) or derivative.

DispatchScriptEvent(name, cancelable, additionalProperties)

Fire an event on the script interface for the instance (as with

`dispatchEvent()` on the script interface). `name` is a string of the event name. `cancelable` is a boolean indicating if the event can be stopped with `preventDefault()`. The event object will have the default properties as described in [Instance event](#) in the scripting reference. Additional properties can optionally be set by passing an object for `additionalProperties` whose properties will be added to the event object. For example:

```
DispatchScriptEvent("myevent", false, { extraProperty: 5  
})
```

SDKPLUGINBASE INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/base-classes/sdkpluginbase>

The `SDKPluginBase` interface is used as the base class for your plugin in the runtime.

`SDKPluginBase` cannot be directly constructed; it should only be used as a base class.

Note plugins that create a DOM element should derive from [SDKDOMPluginBase](#) instead.

Properties

`this._runtime`

Reference to the associated [Runtime](#) that controls execution of the project.

Methods

`GetRuntime()`

Returns `this._runtime` publicly.

`OnCreate()`

Optional override called by the runtime when the plugin is created. This is done early on in the loading process.

`IsSingleGlobal()`

Return a boolean indicating if the plugin specified it was single-global.

`IsWorldType()`

Return a boolean indicating if the plugin specified it was the "world" type.

`IsRotatable()`

Return a boolean indicating if the plugin specified it was rotatable.

`MustPreDraw()`

Return a boolean indicating if the plugin specified it must pre-draw when compositing effects.

HasEffects()

Return a boolean indicating if the plugin specified it could have effects added to its instances.

SDKTYPEBASE INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/base-classes/sdktypebase>

The `SDKTypeBase` interface is used as the base class for runtime object types in the SDK. An object type corresponds to an object listed in the Project Bar. Object types may have multiple instances.

`SDKTypeBase` cannot be directly constructed; it should only be used as a base class.

Properties

`this._objectClass`

Reference to the [ObjectClass](#) representing the object type that this instance belongs to.

`this._runtime`

Reference to the associated [Runtime](#) that controls execution of the project.

`this._plugin`

Reference to your addon's SDK plugin class, which derives from [SDKPluginBase](#).

Methods

`GetObjectClass()`

Returns `this._objectClass` publicly.

`GetRuntime()`

Returns `this._runtime` publicly.

`GetPlugin()`

Returns `this._plugin` publicly.

`LoadTextures(renderer)`

Optional override called by the runtime when it wants your object type's textures to be created. `renderer` is the same class used in the editor as

[IWebGLRenderer](#). This method should return a promise that resolves when all textures have been loaded.

ReleaseTextures()

Optional override called by the runtime when it wants your object type's textures to be released. This method is synchronous. Release any WebGL textures and drop the references to them.

OnDynamicTextureLoadComplete()

Optional override called by the runtime when a dynamic texture load has completed. If an object is created at runtime that does not already have its textures loaded, the runtime will call `LoadTextures()` but continue running the game while the textures are loaded asynchronously. When they finish loading, the runtime then calls this override so you have an opportunity to update any references to the newly loaded texture.

SDKWORLDINSTANCEBASE INTERFACE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/base-classes/sdkworldinstancebase>

The `SDKWorldInstanceBase` interface is used as the base class for runtime instances for "world" type plugins. It derives from [SDKInstanceBase](#).

`SDKWorldInstanceBase` cannot be directly constructed; it should only be used as a base class.

Note instances that create a DOM element should derive from [SDKDOMInstanceBase](#) instead.

Properties

`this._worldInfo`

Return the [WorldInfo](#) object that represents this instance's state in the "world" (e.g. its size, position, angle etc). In the runtime this is held as a separate object.

Methods

`GetWorldInfo()`

Returns `this._worldInfo` publicly.

`HandleWebGLContextLoss()`

Utility method to enable calling of the `OnWebGLContextLost()` and `OnWebGLContextRestored()` methods.

`OnWebGLContextLost()`

`OnWebGLContextRestored()`

Optional overrides for handling WebGL context loss. This is only necessary if your addon creates any WebGL resources. These overrides are only called if your instance first calls `HandleWebGLContextLoss()` (normally in the constructor to enable these callbacks for the lifetime of the instance). In a context loss event, all WebGL resources have been released, so any references to them must be dropped. In a context restored event the resources may be recreated again if necessary. Alternatively they can be left released if a lazy-loading approach is used.

EVENTBLOCK

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/event-sheet-classes/eventblock>

The `EventBlock` class represents an event block in an event sheet. This is also used as the "current event" in the [EventStack](#).

EventBlocks consist of conditions and actions and are either AND blocks (the default), running when all conditions are met, or OR blocks, running when any condition is met.

Construct tracks the "SOL modifiers" for each EventBlock. These are the [ObjectClasses](#) that the event may pick from, i.e. the SOLs that may be modified by running the event. This is an important consideration when working with events. Alterations to SOLs that are not in the SOL modifiers list are not permitted.

Retriggering events

The `Retrigger()` method is useful for implementing looping conditions. It should be used as such:

- 1 Get the current event stack frame
- 2 Push a new event stack frame
- 3 In a loop:
 - 1 Push a copy of the SOL
 - 2 Retrigger the current event, passing both the old and new stack frames
 - 3 Pop the SOL
- 4 Pop the event stack frame
- 5 Return false from the condition method. (The event has already been executed the required number of times, and if it returns true, Construct will continue to run the event as normal, which is usually unnecessary.)

The following code example demonstrates the necessary calls.

```
MyLoopingCondition()  
{  
    // Get necessary references  
    const runtime = this._runtime;  
    const eventSheetManager = runtime.GetEventSheetManager();  
    const currentEvent = runtime.GetCurrentEvent();
```

```

const solModifiers = currentEvent.GetSolModifiers();
const eventStack = runtime.GetEventStack();

// Get current stack frame and push new one
const oldFrame = eventStack.GetCurrentStackFrame();
const newFrame = eventStack.Push(currentEvent);

for (const item of myArray)
{
    // ... optionally update state here ...

    // Push a copy of the current SOL
    eventSheetManager.PushCopySol(solModifiers);

    // Retrigger the current event, running a single loop iteration
    currentEvent.Retrigger(oldFrame, newFrame);

    // Pop the current SOL
    eventSheetManager.PopSol(solModifiers);
}

// Pop the event stack frame
eventStack.Pop();

// Return false since event already executed
return false;
}

```

Methods

GetEventSheetManager()

Return the associated [EventSheetManager](#).

GetRuntime()

Return the associated [Runtime](#).

GetParent()

Return the parent EventBlock, or `null` if this is a top-level event.

IsOrBlock()

If `true`, this is an OR block, else it is an AND block.

GetSolModifiers()

Return an array of [ObjectClass](#) that the event block may modify.

Retrigger(oldFrame, newFrame)

Re-run the current event. This is useful for implementing looping conditions. Prior to calling this, you must push a new [EventStackFrame](#), and pass both the old and the new stack frames to this call. Be sure to pop the pushed stack frame once complete. See the code sample above.

EVENTSHEETMANAGER

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/event-sheet-classes/eventsheetmanager>

The `EventSheetManager` class manages everything in the runtime relating to the event system. Generally any runtime calls relating to events will be made using `EventSheetManager`, although the [Runtime](#) class provides some shorthand methods. The `EventSheetManager` is typically accessed via the runtime `GetEventSheetManager()` method.

Many methods are only relevant to call in condition, action or expression methods of an addon, such as retrieving the current event. When not running events, methods relating to the events being executed do not apply and may throw exceptions.

Methods

GetRuntime()

Return the associated [Runtime](#).

GetEventStack()

Return the [EventStack](#) representing the current execution stack in the event system.

GetCurrentEventStackFrame()

Return the current [EventStackFrame](#), representing the current execution context in the event system. This is a shorthand for

```
GetEventStack().GetCurrentStackFrame()
```

GetCurrentEvent()

Return the current [EventBlock](#) being executed. This is a shorthand for

```
GetCurrentEventStackFrame().GetCurrentEvent()
```

IsInTrigger()

True if execution is currently within a triggered event.

ClearSol(objectClasses)

For each [ObjectClass](#) in the given array, reset the selected object list (SOL) back to "all picked" state.

PushCleanSol(objectClasses)

PushCopySol(objectClasses)

For each [ObjectClass](#) in the given array, push a new selected object list (SOL) to the SOL stack. `PushCleanSol` pushes cleared SOLs in the "all picked" state, whereas `PushCopySol` pushes a copy of the top SOL. These methods are necessary when retriggering events. Every pushed SOL must have a corresponding `PopSol` call.

PopSol(objectClasses)

For each [ObjectClass](#) in the given array, pop the top SOL on the SOL stack. This must be called after `PushCleanSol` or `PushCopySol`.

EVENTSTACK

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/event-sheet-classes/eventstack>

The `EventStack` class represents the execution stack in the event system. It is analogous to the stack in traditional programming languages, but adapted to the event system. For example triggering an event will push a new event stack frame, run the trigger, pop the event stack frame, and then resume from the calling event. This ensures each level of execution in the event system runs with its own context.

In Construct the main purpose of the event stack is to track the current event. The event stack is accessible via [EventSheetManager](#)'s `GetEventStack()` method.

Methods

GetEventSheetManager()

Return the associated [EventSheetManager](#).

GetRuntime()

Return the associated [Runtime](#).

GetCurrentStackFrame()

Return the current [EventStackFrame](#).

Push(currentEvent)

Push a new [EventStackFrame](#) to the event stack, and return it. The initial current [EventBlock](#) for the new stack frame must be passed to this call. Every push must have a corresponding `Pop` call.

Pop()

Pop the top [EventStackFrame](#) from the event stack. This must be called after every `Push` call.

EVENTSTACKFRAME

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/event-sheet-classes/eventstackframe>

An `EventStackFrame` represents a single frame in the [EventStack](#). This provides context for one layer of execution in the event system, much like a stack in a traditional programming language. Its main purpose is to track the current event.

Methods

GetCurrentEvent()

Return the currently executing [EventBlock](#).

ASSETMANAGER

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/manager-classes/assetmanager>

The `AssetManager` class manages everything in the runtime relating to assets (associated project files). In general project files simply cannot be fetched by their URL, because in preview mode they are only stored locally, and some platforms like Cordova have limitations on being able to fetch URLs so need to use different approaches to read files. `AssetManager` handles all of these details and should always be used to access any other files in the project.

Methods

GetRuntime()

Return the associated [Runtime](#).

async FetchBlob(url)

Fetch a blob from a given URL. Returns a promise that resolves with the fetched blob. Note this method handles various cross-platform details when used to fetch project files so is preferable if the content being requested will be used as a blob.

async FetchJson(url)

As with `FetchBlob()`, but returns the content in JSON format.

async GetProjectFileUrl(url)

Obtain a URL to a given project filename that can be directly fetched. On some platforms this will be translated to a blob URL; in other cases it will simply return the filename if it can already be directly fetched. Note this method returns a promise that resolves with the URL to use.

LAYER

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/model-classes/layer>

The `Layer` class represents a layer in the runtime.

Methods

GetLayout()

Return the [Layout](#) the layer belongs to.

GetRuntime()

Return the [Runtime](#) for this layer.

GetName()

Return a string of the name of the layer.

GetIndex()

Return the zero-based index of this layer on its layout.

SetVisible(v)

IsVisible()

Set or get a boolean determining whether the layer is visible.

GetViewport()

Return a [C3.Rect](#) representing the axis-aligned bounding box of the visible area of the layer in layout co-ordinates.

SetOpacity(o)

GetOpacity()

Set and get the opacity of the layer in the [0,1] range. 0 is fully transparent and 1 is opaque. This changes the alpha component of the layer color.

SetOwnScale(s)

GetOwnScale()

Set and get the layer's scale as a factor.

GetRenderScale()

Get the scale the layer is rendered at. This is the scale relevant to draw calls.

GetDisplayScale()

Get the scale the layer is rendered at. This is the scale relevant for translating co-ordinates from the canvas/window to the layer.

GetNormalScale()

Get the scale of the layer only using its own scale, the layout scale, and the scale rate.

SetScaleRate(r)

GetScaleRate()

Set and get the scale rate of the layer as a multiplier.

SetParallaxX(px)

SetParallaxY(py)

SetParallax(px, py)

GetParallaxX()

GetParallaxY()

Set and get the X and Y parallax ratios for the layer, as multipliers.

SetAngle(a)

GetOwnAngle()

Set and get the layer's angle in radians. Use `C3.toDegrees()` and `C3.toRadians()` to convert from degrees to radians.

GetAngle()

Get the layer's display angle in radians. This is also affected by the layout angle.

GetBackgroundColor()

Return a [C3.Color](#) representing the layer background color. Only the RGB components are used.

SetTransparent(t)

IsTransparent()

Set and get a boolean indicating if the layer background is transparent.

SetBlendMode(bm)

GetBlendMode()

Set and get the layer blend mode, as an index in to the dropdown list used in Construct's *Blend mode* property. E.g. 0 is "normal", 1 is "additive", etc.

MoveInstanceAdjacent(inst, otherInst, isAfter)

Move the [Instance](#) `inst` adjacent to `otherInst` in the Z order. If `isAfter` is true it moves `inst` just after (above) `otherInst` in the Z order; otherwise it moves `inst` just before (below).

CanvasCssToLayer(x, y)

LayerToCanvasCss(x, y)

Translate CSS pixel co-ordinates on the canvas to layout co-ordinates on the layer, and vice versa. Returns `[x, y]`.

DrawSurfaceToLayer(x, y)

LayerToDrawSurface(x, y)

Translate device pixels on the rendered surface to layout co-ordinates on the layer, and vice versa. Returns `[x, y]`.

LAYOUT

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/model-classes/layout>

The `Layout` class represents a layout in the runtime.

Methods

GetRuntime()

Return the [Runtime](#) for this layout.

GetName()

Return a string of the name of the layout.

SetScrollX(x)

SetScrollY(y)

GetScrollX()

GetScrollY()

Set and get the scroll position in layout co-ordinates.

SetScale(s)

GetScale()

Set and get the layout scale as a multiplier. Note that the layout scale affects all layers.

SetAngle(a)

GetAngle()

Set and get the layout angle in radians. Note that the layout angle affects all layers. Use `C3.toDegrees()` and `C3.toRadians()` to convert from degrees to radians.

GetWidth()

GetHeight()

Get the size of the layout.

GetLayerCount()

Return the number of [Layers](#) on this layout.

GetLayer(p)

GetLayerByIndex(i)

GetLayerByName(name)

Get a [Layer](#) on the layout either by its zero-based index or a case-insensitive string of its name. The `GetLayer()` method accepts either an index or a name.

BEHAVIORINSTANCE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/object-classes/behaviorinstance>

The `BehaviorInstance` class represents an instance of a behavior in the runtime. When a behavior is added to an object class, the runtime creates a `BehaviorInstance` for every instance of the object class that is created. The `BehaviorInstance` can then control its associated instance.

Methods

GetSdkInstance()

Return the behavior-specific behavior instance class, which derives from [SDKBehaviorInstanceBase](#).

GetObjectInstance()

Return the [Instance](#) associated with this behavior instance.

GetBehaviorType()

Return the [BehaviorType](#) this behavior belongs to.

GetBehavior()

Return the behavior-specific class that derives from [SDKBehaviorBase](#).

GetRuntime()

Return the [Runtime](#) for this behavior instance.

BEHAVIORTYPE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/object-classes/behaviortype>

The `BehaviorType` class represents a behavior that has been added to an object class. It is the behavior-equivalent of [ObjectClass](#).

Methods

GetSdkType()

Return the behavior-specific behavior type class, which derives from [SDKBehaviorTypeBase](#).

GetRuntime()

Get the [Runtime](#) for the behavior type.

GetObjectClass()

Get the [ObjectClass](#) that the behavior type was added to. Note this can be either an object type or a family.

GetBehavior()

Return the behavior-specific class that derives from [SDKBehaviorBase](#).

GetName()

Return a string of the name of the behavior type.

CONTAINER

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/object-classes/container>

The `Container` class represents a group of [ObjectClass](#) that have been put in a container together.

Methods

GetRuntime()

Return the [Runtime](#) for this container.

GetObjectTypes()

Return a read-only array of [ObjectClass](#) representing the object classes that have been added to the container.

INSTANCE

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/object-classes/instance>

The `Instance` class represents an object instance in the runtime.

General methods

GetWorldInfo()

For "world" type plugins, get the instance's associated [WorldInfo](#). This allows modification of the position, size, angle etc.

GetRuntime()

Get the [Runtime](#) for this instance.

GetSdkInstance()

Get the plugin-specific instance class for this instance, which derives from [SDKInstanceBase](#). See also [Addon interfaces](#) for the public APIs exposed by some of the built-in addons in Construct.

GetObjectClass()

Get the [ObjectClass](#) representing the object type this instance belongs to.

GetPlugin()

Return the plugin class for this instance, which derives from [SDKPluginBase](#).

BelongsToObjectClass(objectClass)

Returns true if this instance's object class is the given object class, or the given object class is a family and this instance's object class is a member of that family.

GetImagePoint(nameOrIndex)

Get an image point from the instance by either its index or a string of its name. Note image points are returned in a [0,1] range, such that 0.5 represents the middle.

IsInContainer()

Returns true if the instance is in a container.

GetSiblings()

Return a read-only array of sibling instances for this instance, i.e. its associated other instances in its container. This is only applicable if the instance is in a container.

GetUID()

Get the unique identifier (UID) for this instance. UIDs are unique integer numbers assigned to every instance, and never change during the lifetime of the instance.

GetIID()

Get the instance identifier (IID) for this instance. IIDs are the zero-based index of this instance in its object type's instance list. Note IIDs can change during the lifetime of the instance; if an instance with a lower IID is destroyed, all instances with higher IIDs are renumbered so the IIDs are contiguous from 0.

GetBehaviorInstances()

Return a read-only array of [BehaviorInstance](#) for this instance.

GetBehaviorInstanceFromCtor(ctor)

Look up a behavior instance by its behavior constructor. For example `GetBehaviorInstanceFromCtor(C3.Behaviors.Platform)` will return the first [BehaviorInstance](#) for the Platform behavior if the instance has one, else `null`.

GetBehaviorSdkInstanceFromCtor(ctor)

As with `GetBehaviorInstanceFromCtor(ctor)`, but returns the behavior-specific behavior instance class (which derives from [SDKBehaviorInstanceBase](#)) instead.

GetInstanceVariableCount()

Return the number of instance variables for this instance.

SetInstanceVariableValue(index, value)

GetInstanceVariableValue(index)

Set or get an instance variable value by its index. Note the type of the instance variable will be preserved.

GetSavedDataMap()

GetUnsavedDataMap()

Return a `Map` to store additional data to associate with this instance. Use string keys only, and ensure keys are unique. The saved data map is written to savegame files so should be used for persistent state. The unsaved data map

is not written to savegame files so should be used for transient storage or caching.

Do not simply add new JavaScript object properties to Construct's runtime classes. This will cause the JavaScript engine to deoptimise performance for all code using the class. These data maps are provided as a convenient alternative. You can also use a `WeakMap` with `Instance` keys to associate data with instances without leaking memory or modifying the instance class at all.

Scene graph methods

GetParent()

Return the parent instance in the hierarchy, or `null` if none.

GetTopParent()

Return the top parent of this instance in the hierarchy (which by definition has no parent itself), or `null` if none.

***parents()**

A generator method that can be used to iterate all the instance's parents, up to the top parent.

GetChildren()

Return an array of all the children that have been added to this instance. The array may be empty if no children have been added.

***children()**

***allChildren()**

Generator methods that can be used to iterate all the instance's children. The `allChildren()` variant is recursive, so will also iterate children-of-children.

AddChild(childInst, opts)

Add another instance as a child of this instance in the hierarchy. This instance becomes its parent. The child will move, scale and rotate with this instance according to the provided options specified in the object `opts`, which supports the following properties:

- `transformX` : move the child with this instance's X position
- `transformY` : move the child with this instance's Y position

- `transformWidth` : scale the child with this instance's width
- `transformHeight` : scale the child with this instance's height
- `transformAngle` : rotate the child with this instance's angle
- `transformZElevation` : move the child with this instance's Z elevation
- `destroyWithParent` : automatically destroy the child if this instance is destroyed

Each option is a boolean which defaults to `false` if omitted, so only `true` properties need to be specified.

Instances can only have one parent. If the given instance is already added as a child of something else, this method will have no effect.

RemoveChild(childInst)

Remove an existing child that was previously added with `AddChild()`. The child is detached from the hierarchy and this instance will no longer act as its parent. The removed child still keeps its own children, if it has any.

OBJECTCLASS

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/object-classes/objectclass>

The `ObjectClass` class represents an object type or a family in the runtime. An object type is a kind of object that appears in the Project Bar, e.g. "Sprite2". Families are groups of object types. Generally object types and families can be treated the same. However in some cases you may need to treat them separately.

The runtime refers to something that is either an object type or a family as an "object class", hence the name `ObjectClass`.

Methods

GetSdkType()

Return the plugin-specific SDK type class, which derives from [SDKTypeBase](#).

GetPlugin()

Return the plugin class for this object class, which derives from [SDKPluginBase](#).

GetRuntime()

Return the [Runtime](#) for this object class.

GetName()

Return a string of the name of this object class.

IsGlobal()

Return a boolean indicating if this is a global object class. Global instances are not destroyed when changing layout.

IsWorldType()

Return a boolean indicating if the associated plugin is a "world" type.

GetBehaviorTypes()

Return a read-only array of [BehaviorType](#) representing behaviors added to this object class.

IsFamily()

Return a boolean indicating if this is an object type (if false) or family (if true).

GetFamilies()

For object types only. Return a read-only array of families (also `ObjectClass`) that this object type belongs to.

GetFamilyMembers()

For families only. Return a read-only array of object types (also `ObjectClass`) that are in this family.

GetInstances()

Return a read-only array of [Instance](#) that have been created.

GetSingleGlobalInstance()

For single-global plugins only. Returns the single-global instance of the object.

GetFirstPicked()

Return the first picked [Instance](#) in an action, condition or expression.

IsInContainer()

Return true if the object class is in a container.

GetContainer()

If the object class is in a container, return the [Container](#) class representing the container. Otherwise returns `null`.

HasSolidBehavior()

HasNoSaveBehavior()

HasPersistBehavior()

Convenience methods to indicate if the given behavior has been added to the object class.

WORLDINFO

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/object-classes/worldinfo>

The `WorldInfo` class represents the state of an instance in the "world" (i.e. the [Layout](#) it is in). This includes information like its position, size, angle, Z order, layer and so on.

Only "world" type plugin instances have an associated `WorldInfo`. It is typically obtained by using the [Instance](#) `GetWorldInfo()` method.

For performance reasons, `WorldInfo` is a separate object in the runtime, rather than using a different base class for world instances.

Modifying geometric properties

For performance reasons, changing the X, Y, angle, width, height or origin does not update the corresponding bounding box, which is stored separately. If any of these properties are changed, you must call `SetBboxChanged()` afterwards to ensure the runtime re-calculates the bounding box.

General methods

GetInstance()

Return the associated [Instance](#) that this `WorldInfo` represents state for.

SetX(x)

SetY(y)

SetXY(x, y)

GetX()

GetY()

Set and get the position of the instance in layout co-ordinates.

OffsetX(x)

OffsetY(y)

OffsetXY(x, y)

Add to the X and Y components of the instance's position. For example

`OffsetX(5)` is equivalent to `SetX(GetX() + 5)`.

SetWidth(w)

SetHeight(h)

SetSize(w, h)

GetWidth()

GetHeight()

Set and get the width and height of the instance in layout co-ordinates.

SetAngle(a)

GetAngle()

Set and get the angle of the instance in radians. Use `C3.toDegrees()` and

`C3.toRadians()` to convert from degrees to radians.

SetOriginX(x)

SetOriginY(y)

GetOriginX()

GetOriginY()

Set and get the origin of the instance as a normalized position in the [0,1] range, i.e. 0.5 is the middle.

Note some plugins control the origin themselves, such as Sprite applying a new origin when the animation frame changes, so changes can be overwritten.

SetBboxChanged()

Mark the instance's bounding box as having been changed. Call this after altering the position, size, angle or origin of the instance.

GetBoundingBox()

Return a [C3.Rect](#) representing the axis-aligned bounding box of the instance in layout co-ordinates.

GetBoundingQuad()

Return a [C3.Quad](#) representing the bounding quad of the instance in layout co-ordinates, which is essentially the rotated bounding box.

SetOpacity(o)

GetOpacity()

Set and get the opacity of the instance in the [0,1] range. 0 is fully transparent and 1 is opaque. This changes the alpha component of the instance color.

SetUnpremultipliedColor(c)

Set the RGB components of the instance color. This applies a built-in color multiply effect which appears like a tint. As with opacity, color values are in the

[0,1] range. The default is RGB 1,1,1 (white) which means the instance appears with normal colors. Pass a [C3.Color](#) as the parameter. The runtime internally uses premultiplied alpha for best rendering quality; in this method the RGB values do not need to be premultiplied with the alpha (opacity) value, since it will apply the premultiplication for you.

GetUnpremultipliedColor()

GetPremultipliedColor()

Get the instance color as a read-only [C3.Color](#), either without or with premultiplied alpha (respectively). The instance color includes the opacity in the alpha channel.

HasDefaultColor()

Returns `true` if the instance color RGBA value equals (1,1,1,1), else false.

SetBlendMode(bm)

GetBlendMode()

Set and get the instance blend mode, as an index in to the dropdown list used in Construct's *Blend mode* property. E.g. 0 is "normal", 1 is "additive", etc.

GetLayer()

Get the [Layer](#) the instance is currently on.

GetLayout()

Get the [Layout](#) the instance currently belongs to.

SetVisible(v)

IsVisible()

Set and get the visible state for the instance. This is a boolean that hides the instance when set to `false`.

Collision methods

SetCollisionEnabled(e)

IsCollisionEnabled()

Set and get a boolean indicating whether collisions are enabled for this instance.

ContainsPoint(x, y)

Test if a point in layout co-ordinates intersects this instance, respecting its collision polygon and collisions enabled flag.

Mesh distortion methods

CreateMesh(hsize, vsize)

Create a mesh for deforming the appearance of the object with the given number of mesh points horizontally and vertically. The minimum size is 2.

ReleaseMesh()

Releases any mesh that has been created, reverting back to default rendering of the object with no mesh distortion. Ignored if no mesh created.

HasMesh()

Return a boolean indicating whether a mesh has been created for this object.

SetMeshPoint(col, row, opts)

Alter a given point in a created mesh given by its zero-based column and row.

`opts` is an object that may specify the following properties:

- `mode` : a string of `"absolute"` (default) or `"relative"`, determining how to interpret the `x`, `y`, `u` and `v` options.
- `x` and `y` : the mesh point position offset, in normalized co-ordinates [0, 1] across the object size. These are allowed to go outside the object bounds. In relative mode these are added to the mesh point's current position.
- `u` and `v` : the texture co-ordinate for the mesh point, in normalized co-ordinates [0, 1]. These are not allowed to go outside the object bounds. These can be omitted, or in absolute mode be set to -1, to indicate not to change the texture co-ordinate from the default.

Note: this method returns a boolean indicating whether you must subsequently call `SetBboxChanged()` to apply the change. This allows all points in the mesh to be efficiently updated without unnecessarily repeatedly calling `SetBboxChanged()`.

Z order methods

ZOrderMoveToTop()

ZOrderMoveToBottom()

Move the instance to the top or bottom of the Z order on its current layer.

ZOrderMoveToLayer(layer)

Move the instance in the Z order to the given [Layer](#). If the same layer it is currently on is specified, the call is ignored. If the instance is moved to a new layer, it is inserted to the top of the Z order on that layer.

ZOrderMoveAdjacentToInstance(otherInst, isOnTop)

Move the instance in the Z order to be adjacent to the [Instance](#) `otherInst` (note this is passed as an `Instance`, not a `WorldInfo`). If `isOnTop` is true, this instance will be moved directly on top of `otherInst` in the Z order; otherwise it will be directly beneath. This method may move the instance to a different layer, since it will move it to the same layer as `otherInst` is on.

RUNTIME

View online: <https://www.construct.net/en/make-games/manuals/addon-sdk/runtime-reference/runtime>

The `Runtime` class controls execution of a project. It is the equivalent of an [IProject](#) at runtime.

Events

The following events are fired on the runtime dispatcher, which is accessed using `runtime.Dispatcher()`. For example to add an "instancedestroy" event, use

```
runtime.Dispatcher().addEventListener("instancedestroy",  
callback).
```

"instancedestroy"

Fired when any instance is destroyed. The callback receives an event object with an `instance` property referring to the [Instance](#) that was destroyed. Use this event to ensure all references to destroyed instances are dropped.

"afterload"

Fired after the `LoadFromJson` call after the rest of the runtime has finished loading. This means all objects are available and can be looked up by their UID. For example to save a reference to an instance, save its UID to JSON, load its UID and store it in `LoadFromJson()`, and then look it up with `GetInstanceByUID()` in the "afterload" event.

Methods

Dispatcher()

Return the runtime event dispatcher. This is where runtime events are fired. For example use `runtime.Dispatcher().addEventListener(...)` to listen for a runtime event.

GetAssetManager()

Return the project's [AssetManager](#), which is used to load sub-resources.

AddLoadPromise(promise)

Only valid while the project is still loading. Add a promise that the runtime will wait to resolve before starting the first layout. This is useful if you want to make

sure your addon loads a dynamic resource before the game starts.

Single-global plugins create their instance before loading, so this method can be used in single-global instance constructors. Otherwise it can only be used in the plugin or behavior constructor.

IsInWorker()

Return true if the runtime is hosted in a worker. The DOM will be unavailable.

IsPreview()

Returns true if running in Construct 3's preview mode.

GetAllObjectClasses()

Return a read-only array of all [ObjectClass](#) in the project. Note this includes families.

GetObjectClassByName(name)

Look up an [ObjectClass](#) by a case-insensitive string of its name. Note this can return a family.

GetObjectClassBySID(sid)

Look up an [ObjectClass](#) by a SID (Serialization ID), which is a unique number assigned to every ObjectClass. Note this can return a family.

GetSingleGlobalObjectClassByCtor(ctor)

Look up a single-global plugin's [ObjectClass](#) by its plugin constructor function, e.g. `C3.Plugins.Facebook`. Returns `null` if the plugin is not added to the project.

CreateInstance(objectClass, layer, x, y)

Create and return a new [Instance](#) of an [ObjectClass](#) on the given [Layer](#) at a position.

DestroyInstance(inst)

Destroy an [Instance](#).

GetObjectCount()

Get the total number of instances created.

GetInstanceByUID(uid)

Look up an [Instance](#) by its UID. If none exists with the given UID, returns `null`.

GetEventSheetManager()

Return the [EventSheetManager](#) that handles the event system.

GetEventStack()

Return the [EventStack](#). This is a shorthand for

```
GetEventSheetManager().GetEventStack().
```

GetCurrentEventStackFrame()

Return the current [EventStackFrame](#). This is a shorthand for

```
GetEventSheetManager().GetCurrentEventStackFrame().
```

GetCurrentEvent()

Return the current [EventBlock](#). This is a shorthand for

```
GetEventSheetManager().GetCurrentEvent().
```

GetCanvasClientX()

GetCanvasClientY()

Return the offset of the canvas in the document in CSS pixels.

GetCanvasCssWidth()

GetCanvasCssHeight()

Return the size of the canvas in the document in CSS pixels.

GetSampling()

Return one of `"nearest"`, `"bilinear"` or `"trilinear"`, reflecting the project *Sampling* property.

UpdateRender()

Call to indicate that something visible has changed. Most runtime code calls this automatically. However by default if this is not called during a tick, the runtime will skip drawing a frame on the assumption nothing visible has changed.

GetWebGLRenderer()

Return the [WebGLRenderer](#) for the runtime, which is responsible for rendering graphics.

GetMainRunningLayout()

Return the main [Layout](#) that is currently running.

SetTimeScale(t)

GetTimeScale()

Set and get the timescale as a multiplier.

GetDt(inst)

Get the current delta-time (time the last frame took) in seconds. You can optionally pass an [Instance](#) to get delta-time using the object's own timescale.

GetStartTime()

Get the timestamp in milliseconds at the time the runtime started up.

GetGameTime()

Get the in-game time in seconds, which can be affected by time scaling.

GetWallTime()

Get the in-game time in seconds without taking in to account time scaling (aka the "wall clock" time).

GetTickCount()

Get the number of ticks that have elapsed so far.

GetProjectName()

GetProjectVersion()

Return a string of the name and version of the project.

GetProjectUniqueld()

Return a string representing a unique identifier for this project.

SetPixelRoundingEnabled(e)

IsPixelRoundingEnabled()

Set and get a boolean indicating whether pixel rounding is enabled.

InvokeDownload(url, filename)

Invoke a download of the given URL and use the provided filename. The URL can be a blob URL.

Random()

Generate a random number in the range [0,1), which is the same range as `Math.random()`. Use this method to allow the runtime control over the random number generator, e.g. setting a fixed seed to reproduce the same random sequence.

SetSuspended(suspend)

Pass `true` to suspend the runtime or `false` to resume it if paused. When

suspended, the entire runtime halts and stops processing events or drawing the screen. This is done by default when the window or app goes in to the background.

Make sure that suspend and resume calls are paired one-to-one. For example do not suspend once but resume twice.

